

Network Camera

User's Guide

Software Version 1.0

SNC-RZ25N/RZ25P

Owner's Record

The model and serial numbers are located on the bottom. Record the serial number in the space provided below. Refer to these numbers whenever you call upon your Sony dealer regarding this product.

Model No.	
Serial No.	

WARNING

To prevent fire or shock hazard, do not expose the unit to rain or moisture.

To avoid electrical shock, do not open the cabinet. Refer servicing to qualified personnel only.

WARNING

This installation should be made by a qualified service person and should conform to all local codes.

WARNING

A readily accessible disconnect device shall be incorporated in the building installtion wiring.

WARNING (for Installers only)

Instructions for installing the equipment on the ceiling: After the installtion, ensure the connection is capable of supporting four times the weight of the rquipment downwards.

CAUTION

The rating label is located on the bottom.

CAUTION for LAN port

For safety reason, do not connect the LAN port to any network devices that might have excessive voltage.

Power Supply

Caution for U.S.A. and Canada

The SNC-RZ25N operates on 24V AC or 12V DC. The SNC-RZ25N automatically detects the power. Use a Class 2 power supply which is UL Listed (in the U. S. A.) or CSA-certified (in Canada).

Caution for other countries

The SNC-RZ25P operates on 24V AC or 12V DC. The SNC-RZ25P automatically detects the power. Use a power supply rated 24 V AC or 12 V DC witch meets the requirements for SELV (Safety Extra Low Voltage) and complies with Limited Power Source according to IEC 60950.

For customers in the U.S.A. (SNC-RZ25N only)

This equipment has been tested and found to comply with the limits for a Class B digital device, pursuant to Part 15 of the FCC Rules. These limits are designed to provide reasonable protection against harmful interference in a residential installation. This equipment generates, uses, and can radiate radio frequency energy and, if not installed and used in accordance with the instructions, may cause harmful interference to radio communications. However, there is no guarantee that interference wll not occur in a particular installation. If this equipment does cause harmful interference to radio or television reception, which can be determined by turning the equipment off and on, the user is encouraged to try to correct the interference by one or more of the following measures:

- Reorient or relocate the receiving antenna.
- Increase the separation between the equipment and receiver.
- Connect the equipment into an outlet on a circuit different from that to which the receiver is connected.
- Consult the dealer or an experienced radio/TV technician for help.

You are cautioned that any changes or modifications not expressly approved in this manual could void your authority to operate this equipment.

The shielded interface cable recommended in this manual must be used with this equipment in order to comply with the limits for a digital device pursuant to Subpart B of Part 15 of FCC Rules.

If you have any questions about this product, you may call:

Sony's Business Information Center (BIC) at 1-800-686-SONY(7669)

or Write to: Sony Customer Information Services Center

6900-29, Daniels Parkway, PMB 330 Fort Myers, Florida 33912

Declaration of Conformity

Trade Name: SONY
Model No: SNC-RZ25N
Responsible Party: Sony Electronics Inc.
Address: 16450 W. Bernardo

Dr, san Diego, CA

92127 USA 858-942-2230

Telephone No: 858-942-2230

This device complies with Part 15 of the FCC Rules. Operation is subject to the following two conditions: (1) This device may not cause harmful interference, and (2) this device must accept any interference received, including interference that may cause undesired operation.

NOTICE TO USERS

© 2004 Sony Corporation. All rights reserved. This manual or the software described herein, in whole or in part, may not be reproduced, translated or reduced to any machine readable form without prior written approval from Sony Corporation.

SONY CORPORATION PROVIDES NO WARRANTY WITH REGARD TO THIS MANUAL, THE SOFTWARE OR OTHER INFORMATION CONTAINED HEREIN AND HEREBY EXPRESSLY DISCLAIMS ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE WITH REGARD TO THIS MANUAL, THE SOFTWARE OR SUCH OTHER INFORMATION. IN NO EVENT SHALL SONY CORPORATION BE LIABLE FOR ANY INCIDENTAL, CONSEQUENTIAL OR SPECIAL DAMAGES, WHETHER BASED ON TORT. CONTRACT, OR OTHERWISE, ARISING OUT OF OR IN CONNECTION WITH THIS MANUAL, THE SOFTWARE OR OTHER INFORMATION CONTAINED HEREIN OR THE USE THEREOF.

Sony Corporation reserves the right to make any modification to this manual or the information contained herein at any time without notice.

The software described herein may also be governed by the terms of a separate user license agreement.

Microsoft, Windows, Internet Explorer and MS-DOS are registered trademarks of Microsoft Corporation in the United States and/or other countries.

Java is a trademark of Sun Microsystems, Inc. in the United States and other countries.

Intel and Pentium are registered trademarks of Intel Corporation or its subsidiaries in the United States and other countries.

All other company and product names are trademarks or registered trademarks of the respective companies or their respective makers.

Table of Contents

Overview
Features 6
How to Use This User's Guide7
Precautions7
Operating Precautions7
System Requirements8
Preparation
Assigning the IP Address to the Camera
Program 9
Accessing the Camera Using the Web Browser 11
Basic Configuring by the Administrator 13
Operating the Camera
Administrator and User14
Logging in to Homepage — Welcome Page 15
Logging in as a User
Displaying the setting window for the
administrator directly
About Viewers
Configuration of Main Viewer
Camera Control Section
Monitor Image
Controlling the Monitor Image20
Monitoring the camera image
Zooming in the monitor image
Capturing a Monitor Image21
Capturing a monitor image
Saving the captured image21
Operating the camera22
Operating by using the Control panel
Controlling via the control panel
Control the camera in the monitor window 22
Zoom an image by the camera zoom bar 23
Moving the camera to the preset position 23
Controlling the camera on a panorama image . 24
Facing the camera toward the specified point 24
Sending an Image File25
Sending a Monitor Image via E-mail
Sending a Monitor Image to an FTP Server 25
Recording a Still Image in the Memory of the
Camera
Controlling Alarm output 1, 2
Controlling Day/Night Function26
Switching TCP/UDP Transmission Mode 27

Administrating the Camera	
Basic Operations of Administrator Menu	.28
How to set Administrator menu	
Configuration of Advanced mode Menu	.29
Configuring the System — System setting	
menu	.31
System Tab	
Date & time Tab	
Initialize Tab	
System log Tab	
Access log tab	
Setting the Camera Image and Audio	
— Camera setting Menu	.34
Common Tab	
Picture Tab	.36
Day/Night Tab	.37
MPEG4 Tab	.38
JPEG Tab	.38
Reset Tab	.39
Configuring the Network — Network setting	
Menu	.40
Network Tab	.40
Wireless Tab — Setting of Wireless	
Connection	
Wireless authentication Tab - Setting the Wirele	
Authentication	
PPPoE Tab - Setting of PPPoE Connection	
Dynamic IP address notification Tab — Notifyi	ng
the IP Address	
Setting the User — User setting Menu	
Setting the Security — Security setting Menu .	.45
Sending an Image via mail — e-Mail (SMTP)	
setting Menu	.46
Common Tab — Setting the SMTP Function	
Alarm sending Tab — Setting the mail sending	5
mode when detecting the alarm	.47
Periodical sending Tab — Setting the periodical	
mail sending mode	.48
Sending Images to FTP Server	
— FTP client setting Menu	.49
Common Tab — Setting the FTP Client	40
Function	.49
	50
action when detecting the alarm	
Periodical sending Tab — Setting the Periodical FTP Client Activity	
•	. 51
Recording Images in Memory — Image memory setting Menu	52
Common Tab — Setting the Image memory	.32
Function	52
Alarm recording Tab — Setting the Image	. 52
Memory Function when Detecting the Alarm	53
Periodical recording Tab — Setting the Periodi	
recording mode	
Directory Structure of Image Memory	

Downloading images from the Camera — F	
server setting Menu	55
Setting the Alarm Output	
— Alarm output setting Menu	
Alarm output 1, 2 Tab	
Setting the Operations from the Viewer Page	
Trigger setting Menu	57
Setting the Schedule	
— Schedule setting Menu	59
Setting the Alarm Buffer — Alarm buffer set	tting
Menu	
Setting the Motion Detection Function — Mo	otion
detection setting Menu	61
Setting the Motion Detection Area, Sensitivit	y and
Threshold level	
Saving the Camera Position and Action — P	
position setting Menu	
Preset position tab — Saving PanTilt and Zo	
position	63
Tour Setting Tab — Setting a Tour	
Transmitting with External Equipment Using	g the
External Serial Terminal	
— Serial setting Menu	65
Others	
Using the Supplied Setup Program	
Starting the Setup Program Bandwidth Control Tab	
Date time Tab	
PPPoE Tab	
Rebooting the Camera	
Using the SNC audio upload tool — Transmi	
Audio to Camera	
Installing the SNC audio upload tool	
Connecting the Camera to the Computer	69
Using the SNC audio upload tool	69
Using the SNC video player — Playing Video	
Audio File Recorded on Camera	70
Downloading the SNC video player	
Using the SNC video player	
Using the SNC panorama creator - Creating	a
Panorama Image	
Installing the SNC panorama creator	
Using the SNC panorama creator	
Using the Custom Homepage Installer	
Uploading the Custom Homepage Installer t	
Camera	
Assigning the IP Address to the Camera Usin	
ARP Commands	
Using the SNMP	
1. Inquiry Commands	
2. Setting Commands	
Specifications	78

Features

High-quality monitoring via the network

You can monitor a high-quality live image from the camera using the Web browser on the computer connected to the 10BASE-T or 100BASE-TX network. The maximum frame rate is 30 FPS for the SNC-RZ25N and 25 FPS for the SNC-RZ25P.

Up to 20 users can view the image from one camera at the same time (in JPEG mode).

Available Web browsers

Microsoft Internet Explorer Ver. 5.5 or 6.0 Available OS: Windows 2000/ XP

Remote-controllable high-speed pan/tilt mechanism and high magnification autofocus zoom lens

The camera is provided with a high-speed (100° rotation / second), wide-angle $(-170^{\circ} \text{ to } +170^{\circ})$ pan mechanism, a high-speed (90° rotation / second), wide-angle (-90° to +30°) tilt mechanism, and a high-magnification zoom lens with optical zoom of 18 magnifications, electrical zoom of 12 magnifications, giving 216 magnifications in total.

Wireless LAN

Inserting the Wireless Card SNCA-CFW1 especially designed to use with this camera into the CF card slot enables transmission of images from the camera via wireless LAN.

Image transmission using an E-mail or FTP server

You can send a still image from the camera as an attachment of an E-mail or to an FTP server, at the moment when a trigger by the external sensor input, built-in activity detection function or manual trigger button occurs. You can also send still images sequentially for a determined period before and after the trigger to an FTP server, or send them periodically.

Preset positions and Tour programs

You can save up to 16 preset positions (pan, tilt and zoom positions) of the camera, and up to 5 tour programs composed from the preset positions. You can activate the preset positions by synchronizing with the external sensor input or built-in activity detection function.

Alarm output

The camera is equipped with two sets of alarm outputs. You can use them to control peripheral devices by synchronizing with the external sensor inputs, built-in activity detection function, manual trigger button, Day/ Night function or timer.

Direct panning/tilting

Clicking on the desired point in the displayed window allows you to pan and tilt the camera in the direction of that point

- Microsoft, Windows, Internet Explorer and MS-DOS are registered trademarks of Microsoft Corporation in the United States and/or other countries.
- CCD: Charge-Coupled Device

How to Use This User's Guide

This User's Guide explains how to operate the SNC-RZ25N and SNC-RZ25P Network Camera from a computer.

The User's Guide is written to be read on the computer display.

As this section gives tips on using the User's Guide, read it before you operate the camera.

Jumping to the related page

When you read the User's Guide on the computer display, click on the sentence to jump to the related page.

Software display examples

Note that the displays shown in the User's Guide are explanatory examples. Some displays may be different from the ones which appear as you operate the application software.

Printing the User's Guide

Depending on your system, certain displays or illustrations in the User's Guide, when printed out, may differ from those as portrayed on your screen.

Installation Manual (printed matter)

The supplied Installation Manual describes the names and functions of parts and controls of the Network Camera, connecting examples and how to set up the camera. Be sure to read the Installation Manual before operating.

Precautions

This Sony product has been designed with safety in mind. However, if not used properly electrical products can cause fires which may lead to serious body injury. To avoid such accidents, be sure to heed the following.

Heed the safety precautions

Be sure to follow the general safety precautions and the "Operating Precautions."

In case of a breakdown

In case of system breakdown, discontinue use and contact your authorized Sony dealer.

In case of abnormal operation

- If the unit emits smoke or an unusual smell,
- If water or other foreign objects enter the cabinet, or
- If you drop the unit or damage the cabinet:
- 1 Disconnect the camera cable and the connecting cables.
- 2 Contact your authorized Sony dealer or the store where you purchased the product.

Operating Precautions

Operating or storage location

Avoid operating or storing the camera in the following locations:

- Extremely hot or cold places
- Exposed to direct sunlight for a long time, or close to heating equipment (e.g., near heaters)
- Close to sources of strong magnetism
- Close to sources of powerful electromagnetic radiation, such as radios or TV transmitters
- Locations subject to strong vibration or shock

Ventilation

To prevent heat buildup, do not block air circulation around the camera.

Transportation

When transporting the camera, repack it as originally packed at the factory or in materials of equal quality.

Cleaning

- Use a blower to remove dust from the lens or optical filter
- Use a soft, dry cloth to clean the external surfaces of the camera. Stubborn stains can be removed using a soft cloth dampened with a small quantity of detergent solution, then wipe dry.
- Do not use volatile solvents such as alcohol, benzene or thinners as they may damage the surface finishes.

System Requirements

These are the requirements for the computer that displays the image or controls the camera.

Processor

Pentium III 1 GHz or higher (Pentium 4, 2 GHz or higher recommended)

RAM

256 MB or more

OS

Windows 2000/XP

Web browser

Internet Explorer Ver. 5.5 or Ver.6.0

Preparation

The Preparation section explains what the administrator has to prepare for monitoring the images after installation and connection of the camera.

Assigning the IP Address to the Camera

To connect the camera to a network, you need to assign a new IP address to the camera when you install the camera for the first time.

You can assign an IP address in two ways:

- Using the setup program stored in the supplied CD-ROM (see page 9)
- Using the ARP (Address Resolution Protocol) commands (see page 75)

This section explains how to assign an IP address to the camera using the supplied setup program and how to configure the network.

Before starting, connect the camera to a local network, referring to "Connections" in the supplied Installation Manual.

Consult the administrator of the network about the assigned IP address.


Assigning the IP Address Using the **Setup Program**

- Insert the supplied CD-ROM disc into your CD-ROM drive.
 - After a short time a window will open displaying the files on the CD-ROM.
- Click the **Setup** icon of **IP Setup Program**. The "File Download" dialog opens.
- Click Open.

Note

If you click "Save this program to disk" on the "File Download" dialog, you cannot install correctly. Delete the downloaded file, and click Setup icon again.

- Install the IP Setup Program to your computer following the wizard displayed. If the Software License Agreement is displayed, read it carefully and accept the agreement to continue the installation.
- Start the IP Setup Program. The program detects the SNC-RZ25N or SNC-RZ25P cameras connected to the local network and lists them on the Network tab window.



Click on the camera to which you want to assign a new IP address in the list.


MAC address	IP address	Model	Serial No.	Version No.
08-00-46-ec-47-70	192.168.0.100	SNC-RZ25N	001015	0.55.0

The network settings for the selected camera are displayed.

Set the IP address.

To obtain the IP address automatically from a **DHCP server:**

Select Obtain an IP address automatically.



The IP address, Subnet mask and Default gateway are assigned automatically.



To specify the IP address manually:

Select **Use the following IP address**, and type the IP address, Subnet mask and Default gateway in the relevant boxes.




8 Set the DNS server address.

To obtain the DNS server addresses automatically:

Select Obtain DNS server address automatically.



To specify the DNS server addresses manually: Select Use the following DNS server address, and type the Primary DNS server address and Secondary DNS server address in the relevant boxes.



Note

The Third DNS server address and Fourth DNS server address are invalid for this camera.

9 Set the HTTP port No.



Normally select **80** for the HTTP port No. To use another port number, select the text box and type a port number between 1024 and 65535.

10 Type the Administrator name and Administrator password.



The default settings of both items are "admin."

Note

You cannot change the Administrator name and Administrator password in this step. To change these items, See "Setting the User — User setting Menu" on page 44.

11 Confirm that all items are correctly set, then click **OK**.



If "Setting OK" is displayed, the IP address is correctly assigned.

12 To access the camera directly, double-click the camera name on the list.

MAC address	IP address	Model	Serial No.	Version No.
08-00-46-ec-47-70	192,168.0.100	SNC-RZ25N	001015	0.55.0
			1	
				-
				-

Tip

The factory setting of the camera network is as follows.

IP address: 192.168.0.100 Subnet mask: 255.0.0.0

Wireless LAN setting

Type: Adhoc SSID: snc-rz25 Channel: 11 ch WEP: Nothing

The welcome page of the network camera SNC-RZ25N or SNC-RZ25P is displayed.



Note

If the IP address is not set correctly, the welcome page does not appear after step 12. In this case, try to set the IP address again.

Accessing the Camera Using the Web Browser

When the IP address has been assigned to the camera, check that you can actually access the camera using the Web browser installed in your computer.

Use Internet Explorer as the Web browser.

1 Start the Web browser on the computer and type the IP address of the camera in the URL box.

Address http://192.168.0.100/

The welcome page of "Network Camera SNC-RZ25N" or "Network Camera SNC-RZ25P" is displayed.



2 Click Enter.
The main viewer is displayed.



When the main viewer is correctly displayed, the IP address assignment is completed.

When the main viewer of the camera is displayed for the first time

When you click **Enter**, "Security warning" is displayed. When you click **OK**, the ActiveX control is installed and the main viewer is displayed.



Notes

- If **Automatic configuration** is enabled in the Local Area Network (LAN) Settings on Internet Explorer, the image may not be displayed. In this case, disable **Automatic configuration** and set the Proxy server manually. For setting the Proxy server, consult your network administrator.
- When you install ActiveX viewer on Windows 2000 or Windows XP, you should have logged in the computer as the Administrator.

Tip

Every page of this software is optimized as display character size **Medium** for Internet Explorer.

To display the Welcome page correctly

To operate the welcome page correctly, set the security level of the Internet Explorer to Medium or lower, as follows:

- 1 Select **Tool** from the menu bar for Internet Explorer, then select **Internet Options** and **Security** tab in sequence.
- 2 Click the **Internet** icon (when using the camera via the Internet) or **Local intranet** icon (when using the camera via a local network).
- 3 Set the slider to **Medium** or lower. (If the slider is not displayed, click **Default Level**.)

When using antivirus software in the computer

- When you use antivirus software in your computer, the camera performance may be reduced, for example, the frame rate for displaying the image may be lower.
- The Web page displayed when you log in the camera uses Java Script. The display of the Web page may be affected if you use antivirus software in your computer.



Basic Configuring by the Administrator

You can monitor the image of the camera only logging in with the initial condition of this network camera. You can also set various functions according to the install position, network condition or purpose of the camera. We recommend you configure the following items before monitoring the image from the camera.

Setting contents	Setting menu	
Flip the image according to the installation position (desk top or ceiling).	Image flip (page 35)	
Set the format of the image sent from the camera (MPEG 4 or JPEG).	Video mode (page 34)	
Select the white balance mode according to the installing position (indoor or outdoor).	White balance (page 36)	
Select the brightness of the image sent from the camera.	Exposure mode (page 36) Brightness (page 37)	
Select the quality of the image sent from the camera.	MPEG4 Tab (page 38) JPEG Tab (page 38)	
Select the size of the image sent from the camera.	Image size (page 35)	
Select weather the audio from the external microphone is sent or not.	Microphone (page 36)	
Accord date and time of the camera with those of the computer.	Date & time Tab (page 32)	
Make the setting for sending the monitor image attached to a mail.	e-Mail (SMTP) setting Menu (page 46)	
Set the access right of the user for the camera.	Security setting Menu (page 45)	
Set a place to see beforehand.	Preset positin setting Menu (page 63)	
Prepare a panorama image.	Creating a Panorama Imgae (page 71)	

Operating the Camera

The Operating the Camera section explains how to monitor the image from the camera using the Web browser. Use Internet Explorer as the Web browser. The functions of the camera should be set by the Administrator. For setting the camera, see "Administrating the Camera" on page 28.

Administrator and User

This network camera classifies the people who log in into the **Administrator** and the **User**.

The **Administrator** can use all functions of this network camera including camera setting. The functions the **User** can use are monitoring the image and audio from the camera, and controlling the camera. The **Viewer mode** setting restricts the user's access right, and the user is classified as the one of four types.

Each type of the user can use the following functions.

Firmakina		User			
Function	Administrator	Full	Pantilt	Light	View
Monitor a live image	•	•	•	•	•
Watch date and time	•	•	•	•	•
Control the frame rate (Usable only when JPEG mode is selected)	•	•	_	_	_
Control the image view size	•	•	•	•	_
Zoom a image by the digital zoom	•	•	•	•	_
Save the still image in the computer	•	•	•	•	_
Send an image file to the FTP server	•	•	_	_	_
Send an image attached to a mail	•	•	_	_	_
Record an image on the inside memory of the camera	•	•	_	_	_
Control the Alarm out of the I/O port on the camera main unit	•	•	_	_	_
Switch the Day/Night function mode	•	•	_	_	_
Switch the TCP/UDP transmission mode (Available in MPEG4 mode only)	•	•	_	-	_
Perform the zoom operation	•	•	•	_	_
Call the Preset position	•	•	•	_	_
Control the audio	•	•	•	•	•
Control the setting menu	•	_	_	_	_

• Usable function

- Not usable function

The access rights of the administrator and the user can be set in "Setting the User — User setting Menu" on the Advanced mode menu for the administrator on page 44.

Logging in to Homepage

— Welcome Page

Logging in as a User

1 Start the web browser on the computer and type the IP address of the camera you want to monitor.

Address http://192.168.0.100/

The welcome page of **Network Camera SNC-RZ25N** or **Network Camera SNC-RZ25P** is displayed.



2 Select the viewer.

The usable viewers differ depending on the video mode (page 34) of the camera.

When the video mode is set to **MPEG4**, you can use **ActiveX viewer** only, and viewer selection is not possible. (MPEG4 is default. See illustration on Step 1 above.)

When the video mode is **JPEG**, you can select **ActiveX viewer** or **Java applet viewer**.

For details, see "About Viewers" on page 16.

Welcome page when the video mode is JPEG



- Select the viewer language.
 Click **English** or **Japanese** at the bottom of the welcome page.
- 4 Click Enter.
 The main viewer appears.

With the ActiveX viewer



With the Java applet viewer



Control the camera from the main viewer.

Note

If the Welcome page does not activate correctly, the security level of the Internet Explorer may be set to **Medium** or higher. See "To display the Welcome page correctly" on page 11 and check the security level.

Displaying the setting window for the administrator directly

When the administrator sets the camera functions, the setting window can be displayed directly from the welcome page.

1 Click **Setting** on the welcome page. The following dialog appears.



2 Enter the user name and password for Administrator, then click **OK**.

The user name "admin" and the password "admin" are set at the factory for the Administrator. You can change them on the User setting menu in the Advanced mode menu (see page 44).

The Advanced mode menu appears.



About Viewers

You can use the following viewer according to the **Video mode** setting in the camera setting menu on the Advanced mode menu (page 34).

ActiveX viewer

This viewer can monitor the image in both video modes **MPEG4** and **JPEG**.

You have to install it when you access to the main viewer at the first time.

When you are going to display the main viewer of the camera for the first time

When you log in the network camera using ActiveX viewer for the first time (clicking **Enter** to enter the main viewer), the Security Warning appears. Click **Yes** and install ActiveX Control. You can use all the functions of the viewer by using ActiveX Control.

Java applet viewer

You can select this viewer when the camera video mode is set to **JPEG**. The frame rate is lower than the ActiveX viewer.

The Java applet viewer operates only when Java is installed and Java (Sun) is enabled. If it does not operated correctly, check if the specified Java version has been installed successfully and Java (Sun) is enabled.

To check the Java version

Select **Tool** from the menu bar of Internet Explorer, then select **Internet Option** and the **Advanced mode** tab in sequence, and check the version of Java displayed in **Java** (**Sun**) is one of the versions specified below. If the item **Java** (**Sun**) is not displayed, Java is not installed. You need to install Java.

Java Plug-in Ver. 1.4.2_01, Ver. 1.4.2_02, Ver. 1.4.2_03, Ver. 1.4.2_04

To enable Java Plug-in

Check "Use Java2v1.4.2_xx for <applet> (requires restart)" in "Java (Sun)".

To install Java Plug-in

Download Java 2 Runtime Environment, Standard Edition (JRE) from the homepage of Sun Microsystems, Inc., and install it following the instructions on the installer.

Notes

- If Automatic configuration is enabled in the Local Area Network (LAN) Settings on Internet Explorer, the image may not be displayed. In this case, disable Automatic configuration and set the Proxy server manually. For setting the Proxy server, consult your network administrator.
- When you install ActiveX viewer on Windows 2000 or Windows XP, you should have logged in the computer as the Administrator.

Every page of this software is optimized as display character size **Medium** for Internet Explorer.

Configuration of Main Viewer


This section explains the functions of the parts and controls of the main viewer. For a detailed explanation on each part or control, see the specified pages.

Main viewer

MPEG4 mode*



JPEG mode*



* Refer to the "Camera setting Menu" about the Video mode (page 34).

Main menu



Setting

Click this button to display the setting menu for Administrator. (See "This section explains the basic operations and each option of the Administrator menu." on page 28.)

You can operate this function only when logging in as the administrator.



Home

Displays the Welcome page.



Player

Click this button to download the "SNC video player" application program built in the camera. The SNC video player allows you to play video/audio data recorded on the camera with your computer. (See "Using the SNC video player — Playing Video/Audio File Recorded on Camera" on page 70.)

Camera Control Section

Frame rate



(Displayed only when the camera Video mode (page 34) is set to **JPEG**.)

Selects the frame rate to transmit images.

View size



Selects the view size to be displayed. (page 20)





Digital zoom

Click to change the size of the digital zoom. (page 20)



Capture

Click this button to capture a still image shot by the camera and to store it in the computer. (See "Capturing a Monitor Image" on page 21.)



Control

Click this icon to operate the camera using the PanTilt and Zoom functions.

When you click it, the icon appears and you will be able to control PanTilt and Zoom functions from the

main viewer. (See "Controlling via the control panel" (page 22))

Preset position



Select the Preset position name from the drop-down list. Then, the camera will move to the Preset position that you have stored in memory at "Preset position" menu.

Note

The list box is not displayed when no preset position is memorized.



Control panel icon

Click this icon to display the following control panel.

Control panel



You can control PanTilt, Zoom, and Focus of the camera. (page 22).

PanTilt control

Click the arrow button of the direction in which you want to move the camera. Keep it pressed to move the camera continuously.

To return to the home position, click button.

Zoom control

Press **WIDE** to zoom out, and press **TELE** to zoom in. Zooming continues while the button remains pressed.

Focus control

To focus on a nearby object, press NEAR. To focus on a distance object, press FAR.

By pressing ONE PUSH AF, the focus is set to the optimum position.

Note

To control the focus manually, set "Focus mode" of the camera setting menu to Manual. (page 36)



(Displayed only when the camera Viewer mode (page 44) is set to **Full** and one or more triggers are enabled on the Trigger Setting menu (page 57).)

Select the function you want to use from the list box and click the icon. Then you can send the monitor image of the camera to an FTP server (page 25), send it attached to a mail (page 25), record the image on the built-in memory (page 25) and switch the Alarm out to On/Off (page 26).

Transmission (Switching the TCP/ **UDP** transmission mode)

(Displayed only when the camera Video mode (page 34) is set to **MPEG4** and you are using the ActiveX viewer.)

Each click switches the transmission mode of the video/ audio data among TCP mode, UDP (Unicast) mode and UDP (Multicast) mode. (page 27)

The last selected mode is saved in the computer, and it will be selected at the next starting.



(Volume)

(Displayed when the Microphone (page 36) is set to On.)

Drag the bar of _____ icon to adjust the volume. When you click (1) icon, the icon changes to (1) and the audio output stops. To output the audio, click again.

Note

If the volume icon is not displayed in the case you are using Java applet viewer, Audio codec may not be set **G.711(64kbps)** (page 36) or Java may not be installed correctly.

To check if Java is installed correctly, refer to "Java applet viewer" of "About Viewers" on page 16.

Monitor Image



The image shot by the camera is shown here. Date and time is displayed at the top of the window.

Controlling the Monitor Image


You can monitor the camera image on the monitor window of the main viewer.

Monitoring the camera image

Log in to the home page to display the main viewer. You can see how to log in on page 15, "Logging in as a User".



2 Select the frame rate (only when the camera Video mode is set to **JPEG**).



Click the **Frame rate** list box to select the frame rate for transmitting the image. Selectable frame rates are as follows.

SNC-RZ25N

1, 2, 3, 4, 5, 6, 8, 10, 15, 20, 25, 30

SNC-RZ25P

1, 2, 3, 4, 5, 6, 8, 10, 15, 20, 25

The number refers to the frame number transmitted per 1 second.

For example, if you select 30 fps in SNC-RZ25N, the image is sent at the maximum speed of the connected line (30 fps maximum).

Note

The frame rate options indicate the maximum number of frames that can be transmitted. The number of frames actually transmitted may vary depending on network environments and camera settings (image size and image quality settings).

3 Select the view size.



Click **View size** box list box to select the view size from among **Auto**, 640×480 , 320×240 and 160×120

Auto is determined by the image size specified with Image size on the Camera setting page (page 35).

Zooming in the monitor image

- 1 Click Digital zoom icon.
- 2 Click the point you want to zoom in.
 The image is expanded by about 1.5 times with the clicked point at the center.



The digital zoom icon changes to [2].

3 To cancel zooming in, click [2] icon.

Capturing a Monitor Image

You can capture a monitoring image as a still image and save it in the computer.

Capturing a monitor image

- **1** Monitor the camera image in the monitor window.
- 2 Click Capture icon.

 The still image of the moment when you click is captured, and the still image is displayed in the monitor window.

With the ActiveX viewer



With the Java applet viewer



3 To cancel the still image, click **Cancel** or **Close**.

Saving the captured image

With the ActiveX viewer


- 1 Capture the monitor image.
- 2 Click Save. Save As dialog appears.



- 3 Select JPEG or Bit map as Save as type.
- 4 Type on **File name** and specify **Save in**, then click **Save**.

With the Java applet viewer

- **1** Capture the monitor image.
- Right-click the mouse to display the menu and select **Save with a new name**. **Save Picture** dialog appears.



- 3 Select JPEG or Bit map as Save as type.
- 4 Type in **File name** and specify **Save in**, then click **Save**.

Operating the camera

You can operate the camera from the main viewer.

When you click control icon, the display switches to control panel icon. PanTilt mark and Preset list box are displayed on the upper right of the window.

Notes

When park is displayed at upper right side of the window, you can use Pan/Tilt control function. And by executing the digital zoom when you can control it, park turns gray and you cannot control the camera in the monitor window or in the panorama window, or cannot control zoom in the zoom bar.

By canceling the digital zoom, \clubsuit mark returns to white.

- The PRESET list box is not displayed when no preset position is memorized.
- When Exclusive control mode of "System setting Menu" is set to On and when you click the control icon, the remaining time of operation authority is displayed. If you cannot get the authority to control, waiting time icon appears and the waiting time is displayed.

Operating by using the Control panel

You can operate the camera direction, Zoom, and Focus by using the control panel for the monitor image currentry displayed.

Controlling via the control panel

- 1 Click control icon.
 The control panel icon is displayed.
- 2 Click scontrol panel icon.
 The control panel is displayed.



3 Control each function using the displayed control panel.

Pantilt control

Click the arrow button of the direction in which you want to move the camera. Keep it pressed to move the camera continuously.

To return to the home position, click O button.

Zoom control

Press WIDE to zoom out, and press TELE to zoom in. Zooming continues while the button remains pressed.

Focus control

To focus on a nearby object, press NEAR. To focus on a distance object, press FAR.


By pressing **ONE PUSH AF**, the focus is set to the optimum position.

Note

To control the focus manually, set "Focus mode" of the camera setting menu to **Manual**. (page 36)


Control the camera in the monitor window

Click on the monitor image, and the camera moves so that the clicked portion goes to the center of the display.



Dragging the mouse on the window draws a red frame. If you drag the mouse to box the point you want to

watch, the direction and the zoom position of the camera move to suit to the red frame.



Red zooming frame

Click the left button of the mouse on the still image and drag it.

Zoom an image by the camera zoom bar

When you can control this function, the zoom bar is displayed below the window.

You can specify a location to be zoomed by clicking the zoom bar.

The zoom bar is displayed /not displayed by clicking the icon below the image frame.



Optical WIDE marge icon: Click to move the zoom to the optical WIDE Merge (the same magnification).

Optical TELE marge icon: Click to move the zoom to the optical TELE Merge (18-fold magnification).

Digital TELE marge icon: Click to move the zoom to the digital TELE Merge (216-fold magnification)

Not to display the zoom bar

When you are not going to use the zoom bar, it is not displayed by pressing button under the panorama window.

Note

The zoom bar of the digital area is not displayed when the "Zoom mode" of the camera setting menu is not set to Full.

Moving the camera to the preset position


PRESET list box

Select the preset position name from the drop-down list. Then, the camera will move to the preset position that you have stored in memory at "Preset position setting Menu".



Controlling the camera on a panorama image

When you can control the camera, the panorama widow is displayed under the normal camera window.



In the panorama window, an image of 360° around the camera is displayed as a panorama image. When you click on the displayed panorama image, the camera faces the clicked place.

Creating the panorama image

Create the panorama image with the supplied "SNC panorama creator". Refer to page 71 for details.

Tip

The panorama image is the still image converted from the image taken when you were going to create a panorama image with "SNC panorama creator". When the camera is moved or when the layout around the camera is changed, create the panorama image again.


Facing the camera toward the specified point

1 Create a panorama image with "SNC panorama creator" and display it.



2 Click the point you want to watch on the panorama image.

The camera is moved to face toward the clicked point, and the present image of the point is displayed in the normal camera widow.



Not to display the panorama window

When you are not going to use the panorama image, pressing under the panorama window twice prevents its display.

Sending an Image File

You can send a captured still image with an attached mail or to the FTP server.

To use this function, you need to make the **e-Mail(SMTP)** and **FTP client** active, and set the address properly in the Trigger setting menu on the Administrator menu (page 57).

Sending a Monitor Image via E-mail

- 1 Monitor the image on the monitor window.
- **2** Select **e-Mail** from the Trigger list box.



Click Trigger icon.

The still image of the moment when you click is captured, and the mail attached with the image file is sent to the mail address you have set.

Sending a Monitor Image to an FTP Server

- **1** Monitor the image on the monitor window.
- **2** Select **FTP** from the Trigger list box.



Click Trigger icon.

The still image of the moment when you click is captured, and the image file is sent to the FTP server.

Recording a Still Image in the Memory of the Camera

You can capture a camera image as a still image and record it in the memory of the camera. "Memory" contains **Built-in memory** and **CF memory card**, and you can select one of them in the setting window. To use this function, you need to make **Image memory** active and to set details of the image memory in the trigger setting menu on the Administrator menu (page 57).

- **1** Monitor the image on the monitor window.
- **2** Select **Image memory** from the Trigger list box.



3 Click Trigger icon.

The still image of the moment when you click is captured, and the image file is recorded in the memory of the camera.

Controlling Alarm output 1, 2

You can control the Alarm output 1, 2 On (short-circuit) and Off (open).

To use this function, you need to make **Alarm output 1** or **Alarm output 2** active in the Trigger setting menu on the Administrator menu (page 57).

- **1** Monitor the image on the monitor window.
- 2 Select Alarm output1 or Alarm output2 from the Trigger list box.



Click Trigger icon.
Each click switches the Alarm output between On (short-circuit) and Off (open) alternately.

Tip

For the connection of peripheral devices to the Alarm output of the I/O port, see the supplied Installation Manual.

Controlling Day/Night Function

You can control the Day/Night On (night mode) and Off (day mode). To use this function, you need to make **Day/Night** active in the Trigger setting menu on the Administrator menu (page 58).

- **1** Monitor the image on the monitor window.
- 2 Select **Day/Night** from the Trigger list box.




Click Trigger icon.
Each click switches the Day/Night between On (night mode) and Off (day mode) alternately.

Switching TCP/UDP Transmission Mode

You can select the communication port of the video/ audio data as TCP or UDP.

This function can be used when the Video mode (page 34) is set to **MPEG4** and the ActiveX viewer is used.

- 1 Display the main viewer.
- Click TCP/UDP transmission selector icon. Transmission mode selector dialog appears.



Click one of the buttons TCP, UDP (Unicast) or UDP (Multicast).

TCP: Usually select this.

When **TCP** is selected as the communication port, HTTP communication is adopted for video/audio communication.

HTTP is the protocol used for reading a usual Web

In an environment capable of reading Web page, you can watch or listen to the video/audio by selecting TCP port.

UDP (Unicast): When UDP (Unicast) is selected as the communication port, RTP (Real-time Transport Protocol) is adopted for video/audio communication. As RTP is the protocol for running video/audio data, video/audio can be played smoother than when TCP (HTTP) is selected. If the fire-wall is installed between the camera and the computer, or depending on the network environment, the video/audio may not played properly when **UDP** (Unicast) is selected. In this case, select TCP.

UDP (Multicast): You can select this when the multicast streaming (page 34) is **On**. When **UDP** (Multicast) is selected as the transmission port, RTP (Real-time Transport Protocol) and UDP multicast techniques are adopted for video/audio transmission. By selecting it, the network transmission load of the camera can be reduced. If a router which does not correspond to the multicast or the fire-wall is installed between the camera and the computer, the video/audio may not played properly. In this case, select TCP or UDP (Unicast).

Click **OK** to close the dialog.

If you do not change the transmission setting, click Cancel.



Administrating the Camera

The Administrating the Camera section explains how to set the functions of the camera by the Administrator. For monitoring the camera image, see "Operating the Camera" on page 14.

This section explains the basic operations and each option of the the Administrator menu.

Basic Operations of Administrator Menu

You can set all functions to suit the user's condition in the Advanced mode menu.

Click **Setting** in the welcome page or **f** button in the Easy mode menu to display the Administrator menu.

How to set Administrator menu

- 1 Log in the home page to display the welcome page. You can see how to log in on page 15 "Logging in as a User".
- 2 Click **Setting** in the welcome page.

 The authentication dialog appears. Enter the user name and password for Administrator.

 The user name "admin" and password "admin" are set at the factory for the Administrator.

Administrator menu appears.




The following steps also display the Advanced mode menu.

- ① Click **Enter** in the welcome page to display the main viewer.
- ② Click Setting icon in the main viewer.
- 3 Click the menu name (example: System) on the left side of the Administrator menu.


 The clicked setting menu appears.

Example: System setting menu



4 Select the tab above the setting menu, and set each setting option in the tab.

Example: "System" setting menu "Date & time" tab



See page 29 to 62 for details of setting menu tabs and setting options.

5 After setting, click **OK**. The setting contents become active.

Click **Cancel** to invalidate the set values and return to the previous settings.

Buttons common to every setting menu

The following buttons are displayed on the setting menus where they are necessary. The functions of the buttons are the same on every setting page.



Click this button to validate the settings.



Click this button to invalidate the set values and return to the previous settings.

General note on setting menus

After changing a setting on a setting menu and turn off the power soon, wait at least 10 seconds before turning off the power of the camera.

If the power is turned off immediately, the changed setting may not be stored correctly.

Configuration of Advanced mode Menu



System

Displays the System setting menu. ("Configuring the System — System setting menu" on page 31).

Camera

Displays Camera setting menu for setting of camera image and audio. ("Setting the Camera Image and Audio — Camera setting Menu" on page 34)

Network

Displays the network setting menu for setting of network connection. ("Configuring the Network — Network setting Menu" on page 40)

User

Displays the user setting menu for setting the user name and the password to log in. ("Setting the User — User setting Menu" on page 44)

Security

Displays the security setting menu for specifying the computer allowed to connect to the camera. ("Setting the Security — Security setting Menu" on page 45)

e-Mail (SMTP)

Displays the e-Mail (SMTP) setting menu for sending an e-mail. ("Sending an Image via mail — e-Mail (SMTP) setting Menu" on page 46)

FTP client

Displays the FTP client setting menu for sending an image file to FTP server. ("Sending Images to FTP Server — FTP client setting Menu" on page 49)

Image memory

Displays the image memory setting menu for recording a video/audio file in the built-in memory of the camera. ("Recording Images in Memory — Image memory setting Menu" on page 52)

FTP server

Displays the FTP Server menu for setting the FTP server function of the camera.

("Downloading Images from the Camera — FTP server setting Menu" on page 55)

Alarm output

Displays the alarm out setting menu for the alarm out terminal of the camera. ("Downloading Images from the Camera — FTP server setting Menu" on page 55)

Trigger

Displays the trigger setting menu for the operations when you click the trigger button in the main viewer. ("Setting the Operations from the Viewer Page — Trigger setting Menu" on page 57)

Schedule

Displays the schedule setting menu for FTP client function, e-Mail (SMTP) function, Image memory function and Alarm out function and so on. ("Setting the Schedule — Schedule setting Menu" on page 59)

Alarm buffer

Displays the alarm buffer setting menu for the buffer which records the image and audio on the alarm detection. ("Setting the Alarm Buffer — Alarm buffer setting Menu" on page 60)

Motion detection

Displays the Motion detection setting menu for the motion detection function built into the camera. ("Setting the Motion Detection Function — Motion detection setting Menu" on page 61)

Preset position

Displays the preset position setting menu to register the position you want to save.

"Tour function", which circulates the registered positions, is also set here. ("Saving the Camera Position and Action — Preset position setting Menu" on page 63)

Serial

Displays the serial setting menu to communicate with external equipment through the external serial terminal.

("Transmitting with External Equipment Using the External Serial Terminal — Serial setting Menu" on page 65)

Configuring the System


System setting menu

When you click **System** on the Administrator menu, the System setting menu appears.

Use this menu to perform the principal settings of the software.

The System setting menu is composed of five tabs that are System, Date & time, Initialization, System Log and Access Log.

System Tab



Title bar name

Type a name to display on the title bar up to 32 characters. The characters typed here are displayed on the title bar of the Web browser.

Welcome text

Type a text to show on the welcome page, in HTML format, up to 1,024 characters. Use the
 tag for a line break. (A line break is equivalent to 2 characters.)

Serial number

Displays the serial number of the camera.

Software version

The software version of this camera is displayed.

Default URL

Select the homepage to be displayed when you enter the IP address of the camera in the web address box of the browser.

To display the homepage built in the camera Select /index.html.

To display your individual homepage [When using the flash memory]

You can display your favorite homepage. Store the HTML file in the flash memory using the Custom Homepage Installer included in the supplied CD-ROM. For use of the Custom Homepage Installer, see page 73.

- 1 Select User setting/user/.
- 2 Select Flash memory in "Select root directory".
- 3 Type the path of the HTML file in the text box up to 64 characters.

[When using a CF card]

Write the HTML file of the prepared homepage in the recommended CF card, and change the setting of "Default URL" as follows. The original home page can be used.

- 1 Select User setting/user/.
- 2 Insert a recommended CF card that includes the HTML file of your original home page into the CF card slot of the camera.
- **3** Select **A-slot** in "Select root directory".
- 4 Input the pass of the page you want to display in the text box. (up to 64 letters and numbers)

Tip

Even when you select **User setting/user/**

User/, the home page inside the camera can be displayed by typing the following URL in the address box of the browser.

Example: When the IP address of the camera is set to 192.168.0.100

http://192.168.0.100/en/index.html

Exclusive control mode

Controls the authority to operate PanTilt, Zoom and some functions of the camera.

When **Off** is selected, multiple uses can control PanTilt and Zoom at the same time. When multiple users control them at the same time, zoom has precedence over PanTilt.

When **On** is selected, only one user can control. Set the operation time for one user in "Operation time". If a user tries to operate during operation by another user, the authority is controlled by the settings of "Operation time" and "Maximum wait number".

Operation time

Sets the time length for a user having the control authority. Selectable range is from 10 to 600 seconds. This is effective when "Exclusive control mode" is **On**.

Maximum wait number

Sets the number of users who can wait for their turn for control authority during operation by one user. Selectable number is from 0 to 10. This is effective when "Exclusive control mode" is **On**.

Notes

- To use Exclusive control mode, the date and time of the camera and the connected computer must be set correctly at first.
- To use Exclusive control mode, do not set Cookie of the browser to "Disable". When "Disable" is selected, this mode cannot be used.
- To change the settings of Exclusive control mode, click the "Update" button of the browser to reflect the changed contents.

OK/Cancel

See "Buttons common to every setting menu" on page 29.

Date & time Tab



Current date & time

Displays the date and time set on the camera.

Note

After you have purchased the camera, be sure to check the date and time of the camera and set them if necessary.

PC clock

Displays the date and time set on your computer.

Date & time format

Select the format of date and time to be displayed on the main viewer from the drop-down list.

You can select from among **yyyy-mm-dd hh:mm:ss** (year-month-day hour:minute:second), **mm-dd-yyyy hh:mm:ss** (month-day-year hour:minute:second), and

dd-mm-yyyy hh:mm:ss (day-month-year hour:minute:second).

Adjust

Select to set the day and time.

Keep current setting: Select when you do not need to set the date and time.

Synchronize with PC: Select when synchronizing the camera's date and time with those of the computer.

Manual setting: Select when you want to set the camera's date and time manually.

Select the lower 2-digits of year, month, date, hour, minutes and seconds from each drop-down list.

Synchronize with NTP: Select when synchronizing the camera's date and time with those of the time sever called NTP server (Network Time Protocol). Set the **NTP saver name** and the **Interval**.

NTP server name

Type the host name or IP address of the NTP server, up to 64 characters.

Interval time

Select the interval at which you want to adjust the camera's time referring to the NTP server' time, between 1 and 24 hours. The set interval is a guide, and does not indicate the exact time.

Note

The setting time may not accord with the exact time according to the network environment.

Time zone

Set the time difference from Greenwich Mean Time in the area where the camera is installed.

Select the time zone where the camera is installed from the drop-down list.

Automatically adjust clock for daylight saving time changes

When you select it, the clock is automatically adjusted according to the daylight saving time of the selected time zone.

Note

If the time zone selected on the **Time zone** menu is different from that set on the computer, the time is adjusted using the time zone difference and set on the camera.

OK/Cancel

See "Buttons common to every setting menu" on page 29.

Initialize Tab



Reboot

Reboots the camera.

Click **Reboot**, and "The SNC-RZ25N/RZ25P will be rebooted. Are you sure?" appears. Click **OK** to reboot the camera. It takes about two minutes to start again.

Factory default

Resets the camera to the factory settings.

Click **Factory default**, and "Set up data will be initialized. Are you sure?" appears. When you click **OK**, the network indicator on the camera starts to blink. After adjustments of the default settings have finished, the camera reboots automatically. Do not turn off the camera until the camera reboots.

Tip

The camera can also be reset to the factory settings by pressing the reset switch on the camera. For details, see the supplied Installation Manual.

Backup setting data

Saves the setting data of the camera in a file. Click **Save**, and follow the instructions on the browser to specify the folder and save the setting data of the camera. The file name preset at the factory is "snc-rz25.cfg."

Restore setting

Loads the stored setting data of the camera. Click **Browse** and select the file in which the setting data is stored. Then, click **OK**, and the camera is adjusted according to the loaded data and restarted.

Note

With Restore setting, some items in the Network setting menu (page 40) cannot be restored.

Delete user setting URL

By pressing **Delete**, you can delete the home page recorded on the flash memory of the camera with Custom Homepage Installer (page 73).

Delete panorama image

By pressing **Delete**, you can delete the panorama image recorded on the camera with SNC panorama creator (page 71).


Firmware upgrade

Use this when upgrading the camera software. Click **Browse** and specify the file for upgrading, then click **OK**. "Upgrade firmware? Are you sure?" is displayed. Click **OK** and upgrading starts. After completion, the camera starts again.

Notes

- Use only the upgrade up file special to this camera. If you do not, a problem may occur.
- Do not turn off the camera until the upgrading will be completed.

System log Tab




System log

The data of the software activity of the camera are recorded in this. It includes data that are useful when a problem occurs.

Click **Reload** to reload to the latest data.

Access log tab



Access log

The access record of the camera is displayed. Click **Reload** to reload to the latest data.

Setting the Camera Image and Audio

— Camera setting Menu

When you click **Camera** on the Administrator menu, the Camera setting menu appears.
Use this menu to set the functions of the camera.
The Camera setting menu consists of 5 tabs: **Common**, **Picture**, **MPEG4**, **JPEG** and **Reset**.

Common Tab



Video mode

Select the output format of the camera image. **MPEG4** or **JPEG** can be selected.

Unicast streaming

Specify the transmission port number of the video data and audio data used when **UDP** (**Unicast**) is selected with the TCP/UDP transmission switching icon in the main viewer

Video port number: Specify the transmission port number of the video data. It is initially set to 50000. Specify an even number from 1024 to 65534.

Audio port number: Specify the transmission port number of the audio data. It is initially set to 50002. Specify an even number from 1024 to 65534.

Multicast streaming

Set whether the camera uses the Multicast streaming or not. It reduces sending load on the camera by making the computer of the same segment network (not above the router) receive the same transmitting data.

Select **On** to allow the multicast sending and **Off** not to allow.

When you select On, set Multicast address, Multicast video port number and Multicast audio port number properly.

Multicast address: Type the multicast address used on the Multicast streaming.

Multicast video port number: Specify the video transmission port number used on the Multicast streaming.

Multicast audio port number: Specify the audio transmission port number used on the Multicast streaming.

Image size

You can select the image size sent from the network camera.

 $640 \times 480 \text{ (VGA)}, 480 \times 360, 384 \times 288, 320 \times 240$ (QVGA), 256 × 192 or 160 × 120 (QQVGA) can be selected.

Cropping

When the image size is set to 640×480 (VGA), you can crop a portion of the image and display the cropped image on the computer. With the cropping, the transmitting data size, and thus, the network load is reduced and a higher frame rate is obtained.

Select **On** for cropping the image, or **Off** for no cropping.

- When Cropping is set to **On**, Motion detection function does not work.
- While Cropping is set to **On**, the image of the composite video signal output from the video output connector of the camera may be distorted.


To crop an image

- 1 Set the Image size to $640 \times 480(VGA)$. The **Cropping** is displayed.
- Set the Cropping to On and click the Area setting

The "Area setting" display appears.

Specify the cropping area.

Click the left button of the mouse on the still image and drag it diagonally. The red frame that appears as you drag indicates the cropping area.



frame

Click the left button of the mouse on the still image and drag it.

- 4 Click **OK** at the bottom of the window. The cropped image is displayed on the main viewer.
- To close the image, click in the upper-right corner.

Image mode

Selects the image output from the camera.

Select Frame or Field.

When **Frame** is selected, the horizontal resolution increases. But when a moving object is displayed, its edge may be jagged.

Note

This function cannot be used when the image size is set to QVGA or less.

Color

Select Color or Monochrome for the image.

E. flip

The image can be displayed upside down. Select Off when you fix the camera to the ceiling. Select **On** when you install the camera on the rack or the desk.

Note

The camera restarts when you have changed the setting of E. flip.

Zoom mode

Selects Zoom mode.

When **Full** is selected, an image can be zoomed up to 18X optical zoom and 12X digital zoom, 216X zoom in total.

when **Optical** is selected, an image can be zoomed up to 18X optical zoom.

Focus mode

Selects Focus mode. When **Auto** is selected, the focus is automatically adjusted.

When **Manual** is selected, the focus can be adjusted by using the **Near Far** and **One Push Focus** buttons of the control panel displayed from the main viewer.

Microphone

Select whether you send the audio from the microphone input connector. Select **On** to send the audio from this network camera.

Note

When you change the Microphone setting, click **Refresh** of the browser to reflect the change in the opening main viewer page.

Mic volume

Set the volume level of the audio input from the $\$ microphone input connectors. It is adjustable from -10 to +10.

Audio codec

Select the bit rate when you send the audio from the microphone input connectors. G.711 (64kbps), G.726 (40kbps), G.726 (32kbps), G.726 (24kbps) or G.726 (16kbps) can be selected.

Note

When the bit rate is set to other than G.711(64bps), the audio is not output in the case you are using Java applet viewer.

Speaker output

Set whether you output the audio which is input to the audio input connectors of your computer to the speaker (active speaker for example) connected to the camera line output connectors by using SNC audio upload tool included in the supplied CD-ROM.

Select **On** to accept the audio data transmission from SNC audio upload tool.

OK/Cancel

See "Buttons common to every setting menu" on page 29.

Picture Tab

You can set the color condition, exposure, etc. of the camera.



White balance

Select the white balance mode from among Auto, Indoor, Outdoor, One push WB, ATW, and Manual.

Auto: to automatically adjust the color to be close to the one you are viewing. (approximately 3000K to 7500K)

Indoor: to adjust the white balance for shooting indoors under an incandescent lamp (about 3200 K)

Outdoor: to adjust the white balance for shooting outdoors (about 5800 K)

One push WB: The **One push trigger** button is displayed. Click the button to adjust the white balance instantly.

ATW: Makes the subject to lights and automatically adjusts to re-create the original color. (approximately 2000k to 10000k)

Manual: When you select this, **R** Gain and **B** Gain are displayed and you can set them. Selectable gain values are from 0 to 255.

Exposure mode

Select the exposure mode of the camera from among **Full auto**, **Shutter priority**, **Iris priority**, and **Manual**. The setting items required for each setting appear.

Full auto: The camera executes the gain adjustment and the iris adjustment automatically. In this case, the shutter speed is fixed.

When you select this, **Slow shutter** and **Backlight compensation** are displayed and you can set them as you require.

Shutter priority: The camera executes the gain adjustment and the iris adjustment automatically and you can select the shutter speed. When you select it, Shutter speed are displayed and you can set them.

Iris priority: Gain and Shutter speed of the camera can be adjusted automatically, and Iris can be selected. When it is selected, **Iris** and **Slow shutter** are displayed and they can be set.

Manual: You can set the exposure manually. When you select it, **Shutter speed**, **Gain** and **Iris** are displayed and you can set them.

According to the Exposure mode, the following setting options are displayed.

Slow shutter

Set the Slow shutter. When **On** is selected, auto exposure setting including the long time exposure is set to suit to the brightness of the scene.

Backlight compensation

You can set **On** or **Off** of the exposure compensation. When you select **On**, the exposure compensation function starts to work.

Shutter speed

Select the shutter speed of the camera from the list box. Selectable values of the shutter speed are as follows **SNC-RZ25N**

1/10000, 1/6000, 1/4000, 1/3000, 1/2000, 1/1500, 1/1000, 1/725, 1/500, 1/350, 1/250, 1/180, 1/125, 1/100, 1/90, 1/60, 1/30, 1/15, 1/8, 1/4, 1/2, 1/1

SNC-RZ25P

1/10000, 1/6000, 1/3500, 1/2500, 1/1750, 1/1250, 1/1000, 1/600, 1/425, 1/300, 1/215, 1/150, 1/120, 1/100, 1/75, 1/50, 1/30, 1/25, 112, 1/6, 1/3, 1/2, 1/1

Gain

Select the gain from the list box.

Selectable values of the gain are -3dB, 0dB, 2dB, 4dB, 6dB, 8dB, 10dB, 12dB, 14dB, 16dB, 18dB, 20dB, 22dB, 24dB, 26dB, 28Db

Iris

Select the iris from the list box.

Selectable values of the iris are as follows.

Close, 22, 19, 16, 14, 11, 9.6, 8.0, 6.8, 5.6, 4.8, 4.0, 3.4, 2.8, 2.4, 2.0, 1.6, 1.4 (F)

Exposure compensation

Exposure compensation function adjusts the brightness at the AE.

Selectable values of the exposure compensation are as follows.

-10.5dB, -9dB, -7.5dB, -6dB, -4.5dB, -3dB, -1.5dB, 0dB, 1.5dB, 3dB, 4.5dB, 6dB, 7.5dB, 9dB, 10.5dB

Brightness

Tweaks the exposure set in the exposure mode. It is brighter when a large value is selected, and it is darker when a small value is selected. The value among -5 to 5 can be set.

Saturation

Select the saturation in 7 steps, from -3 to 3. Selecting 3 gives the image with the highest saturation.

Sharpness

Select the sharpness in 7 steps, from -3 to 3. Selecting 3 gives the image with the highest sharpness.

Contrast

Select the contrast in 7 steps, from -3 to 3. Selecting 3 gives the image with the highest contrast.

OK/Cancel

See "Buttons common to every setting menu" on page 29.

User preset


You can save the present settings in the camera as the custom, or you can load the settings saved in the camera.

Save: Click to save the present settings of the Picture

Load: Click to load the saved settings. To use them, click **OK**.

Day/Night Tab

Use this tab to set the day/night function of the camera.



The day/night function consists of five tabs.

Disable

Always works in day mode.

Auto

Normally works in day mode. It switches automatically to night mode in a dark place.

Manual

Switch the day/night mode manually. When you select **Manual**, **On** and **Off** are displayed. When you select **On**, the camera works in night mode. When you select **Off**, it works in day mode.

Timer

Normally works in day mode. It switches to night mode at the time you set in the Schedule setting menu. The day/night function normally works in day mode.

Sensor

Controls day/night mode by synchronizing with the sensor input. Select the sensor input with which you want to synchronize: **Sensor input 1** or **Sensor input 2**. While a sensor input is detected, it turns to the night mode.

Note

When you select the day/night function in Trigger setting menu after selecting **Auto**, **Timer** or **Sensor** in the **Day/Night** tab, you can switch the day/night mode from the **Trigger** on the main viewer.

OK/Cancel

See "Buttons common to every setting menu" on page 29.

MPEG4 Tab



Frame rate

Set the frame rate of the MPEG image. Selectable values of the frame rates are as follows. SNC-RZ25N: 1, 2, 3, 4, 5, 6, 8, 10, 15, 20, 25, 30 fps SNC-RZ25P: 1, 2, 3, 4, 5, 6, 8, 10, 15, 20, 25 fps The unit is "fps" (frame number sent per a second).

Bit rate

Set the bit rate of MPEG image transmission for a line. Selectable values are 64, 128, 256, 384, 512, 768, 1024, 1536 and 2048 kbps.

Note

The selected frame rate and bit rate are a tentative value. The actual frame rate and bit rate may be different according to the image size, the shooting scene or the network condition.

I-picture interval

Set the I-picture inserting interval of MPEG4. I-picture is the compression data serving the basic point when the data compressed by MPEG4 is depressed. In the condition that errors tends to happen, such as the network environment variation, the distortion of the image is reduced by selecting a small value. The selectable values are 1, 2, 3, 4 and 5 seconds.

Auto rate control

This function adjusts the frame rate and the bit rate automatically so that the camera plays a smooth image to suit the connected computer environment. If **On** is selected, the rate of MPEG4 image is automatically adjusted.


Note

The maximum transmission rate will be the values set in **Frame rate** and **Bit rate**.

OK/Cancel

See "Buttons common to every setting menu" on page 29

JPEG Tab



Frame rate

Set the maximum frame rate of JPEG image that can be monitored on the computer.

Selectable values of the frame rates are as follows.

SNC-RZ25N

5, 6, 8, 10, 15, 20, 25, 30 fps

SNC-RZ25P

5, 6, 8, 10, 15, 20, 25 fps

Image quality

Set the quality of JPEG image. Selectable values are from **Level 1** to **Level 5**. When **Level 5** is selected, the best picture quality is achieved.

Bandwidth control

When the video mode is set to JPEG, the network bandwidth can be limited. Selectable bandwidths are 0.5, 0.6, 0.7, 0.8, 0.9, 1.0, 2.0, 3.0, 4.0, and Unlimited Mbps. When you do not wish to limit the bandwidth, select **Unlimited**.

OK/Cancel

See "Buttons common to every setting menu" on page 29.

Reset Tab



Reset

Click **Reset**, and "Camera menu setting is reset to default. Are you sure?" is displayed. To reset to default, click **OK**.

Home position setting

Sets the camera position (Pantilt, Zoom and others) of when the power is turning on. By pressing **Set**, the present position is set as the home position.

When you press **Reset**, the home position returns to the factory setting position.



Pan is set to face to front, Tilt is set to horizontal, and Zoom is set to Wide as the factory default.



Configuring the Network

Network setting Menu

When you click **Network** on the Administrator menu, the Network setting menu appears.

Use this menu to configure the network to connect the camera and the computer.

The Network setting menu consists of 3 tabs: **Network**, **Wireless**, **Wireless authentication**, **PPPoE** and **Dynamic IP address notification**.

Network Tab

This section provides the menus for connecting the camera through the network cable.



MAC address

Displays the MAC address of the camera.

Obtain an IP address automatically (DHCP)

DHCP server is installed on the network. Select it when the IP address is assigned by DHCP server. IP address is assigned automatically.

Note

When you set **Obtain an IP address automatically** (**DHCP**), make sure that DHCP server is working on the internet.

Use the following IP address

Select this when a fixed IP address is set.

IP address

Type the IP address of the camera.

Subnet mask

Type the subnet mask.

Default gateway

Type the default gateway.

Obtain DNS server address automatically

Select this to obtain the address of DNS server automatically. It can be set only when **Obtain an IP** address automatically (DHCP) is selected.

Note

When you select "Obtain DNS server address automatically", make sure that DHCP server is active on the network.

Use the following DNS server address

Select this when you set the fixed address as the IP address of DNS server.

Primary DNS server

Type the IP address of the primary DNS server.

Secondary DNS server

Type the IP address of the secondary DNS server, if necessary.

HTTP port number

Normally select **80**. If you want to use a port number other than 80, select the text box and type a port number between 1024 and 65535.

Note

When you have set the HTTP port number to a number other than 80 on the Network setting page or in the Setup Program, access the camera by typing the IP address of the camera on the web browser, as follows:

Example: when HTTP port number is set to 8000



OK/Cancel

See "Buttons common to every setting menu" on page 29.

Wireless Tab — Setting of Wireless Connection

Insert the specified wireless LAN card into the CF card slot of the camera, and set the matters to connect to the wireless network.

Use the optional wirless LAN card SNCA-CFW1 for the wireless connection.



MAC address

Displays MAC address of the wireless LAN card inserted to the CF card slot. If any wireless LAN card is not inserted, "00:00:00:00:00:00" is displayed.

Obtain an IP address automatically (DHCP)

DHCP server is installed on the network. Select it when the IP address is assigned by DHCP server. IP address is assigned automatically.

Note

When you set **Obtain an IP address automatically** (**DHCP**), make sure that DHCP server is working on the internet.

Use the following IP address

Select this when a fixed IP address is set.

IP address

Type the IP address of the camera.

Subnet mask

Type the subnet mask.

Default gateway

Type the default gateway.

Note

When you select "Obtain DNS server address automatically", make sure that DHCP server is active on the network.

Use the following DNS server address

Select this when you set the fixed address as the IP address of DNS server.

Primary DNS server

Type the IP address of the primary DNS server.

Secondary DNS server

Type the IP address of the secondary DNS server.

Type

Select the network connection type **Adhoc mode** or **Infrastructure mode**. Select **Adhoc mode** when connecting to the computer directly, or select **Infrastructure mode** when connecting to the computer via an access point or a radio router. When you select **Adhoc mode**, specify the wireless channel.

Note

The setting of the HTTP port number is common to the setting of the network cable.

Antenna

When you use dedicated wireless card SNCA-CFW1, you can select one of the following antenna settings.

Internal: Suitable for short-range sending and receiving because it is non-directional. Select it when you use the camera inside.

External: Attaching an external antenna to SNCA-CFW1 will enable long-range sending and receiving. Select it when you need long-range sending and receiving with attached external antenna.

Diversity: Uses either the inside or external antenna which has higher sensitivity. In this case, the sensitivity is slightly lower than the settings **Internal** and **External**.

Wireless authentication Tab Setting the Wireless Authentication

Set the authentication necessary for the wireless connection.



SSID

Type the ID to identify the wireless network you want to access using up to 32 ASCII characters (alphanumeric). For your security, be sure to change the factory setting.

WEP

Select **On** when you use the WEP (Wired Equivalent Privacy) keys, or **Off** when you do not use it. The WEP key data settings are valid only when the WEP menu is set to **On**.

WEP key data

Specify up to 4 WEP keys. The length of a WEP key is 40 or 104 bit. A 104-bit WEP key has a higher security level than a 40-bit key. You can type the WEP key either in hexadecimal numbers (0 to 9 and A to F) or ASCII characters (alphanumeric).


When the Type menu is set to **Infrastructure mode**, the WEP key should be the same as that of the access point. When the Type menu is set to **Ad hoc mode**, the WEP key should be the same as that of the communication client.

Notes

- When you remove the wireless LAN card, be sure to first turn off the power of the camera.
- When you use a wireless LAN card, the throughput of communication data through the Ethernet may decrease.

PPPoE Tab - Setting of PPPoE Connection

Use it when you connect the camera with PPPoE (Point-to-Point Protocol over Ethernet). PPPoE connection is the protocol that is widely used in xDSL (digital affiliate line such as ADSL, VDSL or SDSL) as the authentication and connection system.



PPPoE

Set whether you connect the camera using PPPoE function or not. When **On** is selected, PPPoE connection is used.

IP address

When you connect to the network by PPPoE function, IP address obtained at PPPoE connection is displayed.

User ID

Type the user ID for the authentication necessary for PPPoE connection. Type it up to 64 characters.

Password

Type the password for the authentication necessary for PPPoE connection. Type it from 1 to 32 characters.

Re-type password

To certain the password, re-type the characters as them typed in the password box.

Obtain DNS server address automatically

Select it to obtain the address of DNS server automatically.

Use the following DNS server address

Select this when you set the fixed address as the IP address of DNS server.

Primary DNS server

Type the IP address of the primary DNS server.

Secondary DNS server

Type the IP address of the secondary DNS server.

OK/Cancel

See "Buttons common to every setting menu" on page 29

Dynamic IP address notification Tab — Notifying the IP Address

When the DHCP setting is set to **On** or PPPoE setting is set to **On** on the Network tab, you can send notification of the completion of the network settings using the SMTP or HTTP protocol.



e-Mail (SMTP) notification

Select **On** to send an e-Mail when the DHCP setting is completed.

SMTP server name

Type the name or IP address of the SMTP server you want to use for sending an e-Mail, up to 64 characters.

Authentication

Select the authentication required when you send an e-Mail.

Off: Select if no authentication is necessary when an email is sent.

On: When authentication is necessary an e-mail is sent, select one of the authentication methods from the followings.

SMTP: Select if authentication is necessary when an e-mail is sent.

POP before SMTP: Select when **POP before SMTP** is necessary when an e-Mail is sent.

Note

When you set to **On**, make sure to select either or both **SMTP** or/and **POP** before **SMTP**.

POP server name

It is necessary when the **POP before SMTP** is selected in **Authentication**.

Type the POP (receiving mail) server name up to 64 characters. Or type the IP address of the POP server. This setting is necessary when the SMTP server which sends e-mails performs authentication using the POP user account.

User name, Password

Type the user name and Password of the user who has the mail account. This setting is necessary when the SMTP server which sends e-mails performs authentication.

Recipient e-mail address

Type the recipient e-Mail address up to 64 characters. You can specify only one recipient e-Mail address.

Administrator e-mail address

Type the e-Mail address of the camera administrator, up to 64 characters. This is used as the reply address or the address for a system mail from the mail server.

Subject

Type the subject/title of the e-Mail up to 64 characters.

Message

Type the text of the e-Mail up to 384 characters. You can describe the information of the acquired IP address, etc. using the special tags mentioned below.

HTTP notification

Select **On** to output a command to the HTTP server when the DHCP setting is completed. Using this function, you can configure a useful system, for example, to view the access log stored in the HTTP server or start an external CGI program.

URL

Specify the URL to send HTTP commands, up to 256 characters. The URL is normally composed as follows:

http://ip_address[:port]/path?parameter

ip_address: Type the IP address or host name of the host to which you want to connect.

:port: Specify the port number to which you want to connect. If you want to use the well-known port number 80, you do not need to input this value.

path: Type the command name.

parameter: Type the command parameter if necessary. You can use the special tags mentioned below for the parameters.

Proxy server name

When you send HTTP commands via a proxy server, type the name or IP address of the proxy server, up to 64 characters.

Proxy port number

Specify the port number when you send HTTP commands via the proxy server. Set a port number between 1024 and 65535.

Method

Select the HTTP method GET or POST.

OK/Cancel

See "Buttons common to every setting menu" on page 29.

About the special tags

You can use the following five special tags to allow the notification of the settings acquired by the DHCP, such as an IP address. Type the tags in the parameter section of the URL that you describe in the Message field of the HTTP.

<IP>

Use this tag to embed the IP address acquired by the DHCP in the text or parameter.

<HTTPPORT>

Use this tag to embed the specified HTTP server port number in the text or parameters.

<MACADDRESS>

Use this tag to embed the MAC address of the interface whose IP address you have acquired by the DHCP, in the text or parameter.

<MODELNAME>

Use this tag to embed the camera's model name (SNC-RZ25) in the text or parameter.


<SERIAL>

Use this tag to embed the camera's serial number in the text or parameter.

Setting the User — User setting Menu

When you click **User** on the Administrator menu, the User setting menu appears.

Use this menu to set the user names and passwords of Administrator and up to 9 kinds of users (User 1 to User 9), and the access right of each user.



Administrator, User 1 to 9

Specify User name, Password, Re-type password, FTP user and Viewer mode for each user ID.

User name

Type a user name between 5 and 16 characters.

Password

Type a password between 5 and 16 characters.

Re-type password

To confirm the password, type the same characters as you typed in the Password box.

FTP user

Set whether logging in to FTP server is allowed or not. When you need to log in to FTP server, check it.

Viewer mode

If the user is authenticated when the main viewer is displayed, you can select the viewer mode displayed after authentication.

Full: You can operate all functions in this mode.

PanTilt: In addition to the light mode, you can operate PanTilt.

Light: In addition to the view mode, you can select the image size of the main viewer, control digital zoom, and get a still image.

View: You can monitor only the camera image.

Viewer authentication

Set whether the user is authenticated or not when the main viewer is displayed.

When you select **On**, the main viewer is displayed to suit the authenticated user. When you select **Off**, select the view mode of the main viewer page which is displayed without authentication from among **Full**, **PanTilt**, **Light** or **View**.

OK/Cancel


See "Buttons common to every setting menu" on page 29.

Setting the Security

— Security setting Menu

When you click **Security** on the Advanced mode menu, the Security setting menu appears.

Use this menu to limit the computers that can access the camera.



Security function

To activate the security function, select **On**. If you do not wish to use the security function, select **Off**.

Default policy

Select the basic policy of the limit from Allow and Deny for the computers specified on the Network address/Subnet 1 to Network address/Subnet 10 menus below.

Network address/Subnet 1 to Network address/Subnet 10

Type the IP addresses and subnet mask values you want to allow or deny access to the camera.

You can specify up to 10 IP addresses and subnet mask values. For a subnet mask, type 8 to 32.

Select **Allow** or **Deny** from the drop-down list on the right for each IP address/subnet mask .

Tip

The subnet mask value represents the bit number from the left of the network address.

For example, the subnet mask value for "255.255.255.0" is 24.

If you set "192.168.0.0/24" and "Allow," you can allow access from the computers having an IP address between "192.168.0.0" and "192.168.0.255".

Note

You can access the camera even from a computer having an IP address whose access right is set to **Deny**, if you enter the user name and password set for the Administrator boxes in the User setting menu.

OK/Cancel

See "Buttons common to every setting menu" on page 29

Sending an Image via mail — e-Mail (SMTP) setting Menu

When you click **SMTP** on the Administrator menu, the SMTP setting menu appears.

By using Mail (SMTP) function, you can send a mail with attached image which has been shot linked with the external sensor input or with the built-in motion detection function. The image file can also be sent periodically.

e-Mail (SMTP) setting menu is composed of three tabs: **Common**, **Alarm sending** and **Periodical sending**.

Common Tab — Setting the SMTP Function



e-Mail (SMTP)

Select **On** when you use the e-Mail (SMTP) function. The common setting options are displayed below. If you do not wish to use the e-Mail (SMTP) function, select **Off** and click **OK**.

Notes

- During transmission of an image file via mail, the frame rate and operation performance of the monitor image of the main viewer decline.
- While the camera video mode is set to MPEG4, the image of the composite video signal output from the video output connector of the camera may be distorted during mail transmission.
- You cannot send an audio file by using the mail sending function.

SMTP server name

Type the SMTP server name up to 64 characters, or the IP address of the SMTP server.

Authentication

Select the authentication required when you send an e-mail

Off: Select if no authentication is necessary when an email is sent

On: When authentication is necessary an e-mail is sent, select one of the authentication methods from the followings.

SMTP: Select if authentication is necessary when an e-mail is sent.

POP before SMTP: Select when POP before SMTP authentication is necessary when an e-mail is sent.

Note

When you set to **On**, be sure to select either or both **SMTP** or/and **POP before SMTP**.

POP server name

It is necessary when the **POP before SMTP** is selected in **Authentication**.

Type the POP (receiving mail) server name up to 64 characters, or type the IP address of the POP server. This setting is necessary when the SMTP server which sends e-mails performs authentication using the POP user account.

User name, Password

Type the user name and Password of the user who has the mail account. This setting is necessary when the SMTP server which sends e-mails performs authentication.

Recipient e-mail address

Type the recipient e-Mail address up to 64 characters. You can specify up to three recipient E-mail addresses.

Administrator e-mail address

Type the Administrator e-Mail address up to 64 characters.

This address is used for reply mail and sending system messages from the SMTP server.

Subject

Type the subject/title of the e-Mail up to 64 characters. With respect to mail which is sent according to the alarm detection when **Alarm sending** of the alarm tab is set to **On**, the characters standing for the sensor type added to the subject. **S1** is added for sensor input1 detection, **S2** is added for sensor input2 detection, and **MD** is added for motion detection.

Message

Type the text of the E-mail up to 384 characters. (A line break is equivalent to 2 characters.)

OK/Cancel

See "Buttons common to every setting menu" on page 29.

Alarm sending Tab — Setting the mail sending mode when detecting the alarm

Set to send the mail with connection to the alarm detection by the external sensor input or by the built-in motion detection function.



Alarm sending

Select **On** to set to send mail with connection to the alarm detection.

File attachment

Set whether an image file is attached to the mail sent or not.

When **On** is selected, the image file made by the settings below is attached. When **Off** is selected, only the message is sent.

Image file name

Type the file name you want to assign to the image to attach a mail. You can use up to 10 alphanumeric, - (hyphen) and _ (underscore) for naming.

Suffix

Select a suffix to add to the file name.

None: No suffix is added. The Image file name is assigned to the image to be sent via an e-Mail.

Date & time: The date & time suffix is added to the Image file name.

The date/time suffix consists of lower two-digits of year (2 digits), month (2 digits), date (2 digits), hour (2 digits), minute (2 digits), second (2 digits), and consecutive number (2 digits), thus 14-digit number is added to the file name.

Sequence number: A consecutive number of 10 digits between 0000000001 and 4294967295 and two fixed digits 00 is added to the Image file name.

Tip

A consecutive number added to **Date & time** and **Sequence number** is used to identify each of multiple files created with one alarm event.

Sequence number clear

Click **Clear** to reset the Sequence number suffix to 1.

Alarm

Select the connected alarm.

Sensor input1: The external sensor which is connected to sensor input1 of the camera I/O port.

Sensor input2: The external sensor which is connected to sensor input2 of the camera I/O port.

Motion detection: Click **Motion detection** button, and the Motion detection setting menu is displayed. You can set the motion detection function (page 61).

Notes

- Motion detection works only when the camera Video mode is set to MPEG4 and the Cropping is set Off.
- In the case that the synchronized preset position is specified, the alarm event that happens during moving to the preset position will be invalid.

Effective period

Set the period when the alarm detection is effective. **Always:** The alarm detection is always effective.

Schedule: You can specify the period when the alarm detection is effective in the schedule setting in the other section.


Click **Schedule** and the setting menu for the Effective period is displayed. ("Setting the Schedule — Schedule setting Menu" on page 59)

OK/Cancel

See "Buttons common to every setting menu" on page 29.

Periodical sending Tab — Setting the periodical mail sending mode

You can set to send mails periodically.



Periodical sending

Select **On** when you want to send mails periodically. If you select **Off**, Periodical sending is not executed.

Image file name

Type the file name of the image attached to the mail up to 10 alphanumeric, - (hyphen) and _ (under score).

Suffix

Select a suffix added to the file name used when the mail is sent.

None: The name of the sent file will be the Image file

Date & time: The date & time suffix is added to the Image file name.

The date & time suffix consists of lower two-digits of year (2 digits), month (2 digits), date (2 digits), hour (2 digits), minute (2 digits) and second (2 digits), and consecutive number (2 digits), thus 14-digit number is added to the file name.

Sequence number: A consecutive number of 10 digits between 0000000001 and 4294967295 and two fixed digits 00 is added to the Image file name.

Sequence number clear

Click **Clear** and the suffix of the sequence number returns to 1.

Interval

Type the interval at which you want to send a mail periodically. You can set the hour (H) and minutes (M) between 30 minutes and 24 hours (one day).

Effective period

Set the period when the periodical sending is effective. **Always:** The periodical sending is always effective. **Schedule:** You can specify the period when the periodical sending is effective in the schedule setting

in the other section.

Click **Schedule** and the setting menu for the effective period is displayed. ("Setting the Schedule — Schedule setting Menu" on page 59)

OK/Cancel

See "Buttons common to every setting menu" on page


Sending Images to FTP Server

- FTP client setting Menu

menu, the FTP client setting menu appears. Use this menu to set up for capturing and sending still images to an FTP server. By using FTP client function, you can send the image and audio file which has been shot and recorded linked with the external sensor input or with the built-in motion detection function to FTP server. The image file can also be sent periodically. FTP client setting menu is composed of three tabs Common, Alarm sending and Periodical sending.

When you click FTP client on the Administrator mode

Common Tab — Setting the FTP **Client Function**



FTP client function

To activate the FTP client function, select **On**. The FTP client setting page appears.

When you do not wish to use the FTP client function, select Off.

Note

The frame rate and operability on the main viewer may decrease while a file is being transmitted by the FTP client function.

FTP server name

Type the FTP server name to upload still images up to 64 characters, or the IP address of the FTP server.

User name

Type the user name for the FTP server.

Password

Type the password for the FTP server.

Re-type password

To confirm the password, type the same characters as you typed in the Password box.

Passive mode


Set whether you use the passive mode of FTP server or not when connecting to FTP server. Select **On** to connect to FTP server using the passive mode.

OK/Cancel

See "Buttons common to every setting menu" on page 29.

Alarm sending Tab — Setting the FTP client action when detecting the alarm

Set to forward the image and audio file to the specified FTP server linked with the alarm detection by the external sensor input or by the built-in motion detection function.



Alarm sending

Select **On** to send the image and audio file to FTP server linked with the alarm detection.

Remote path

Type the path to the destination up to 64 characters.

Image file name

Type the file name you want to assign to the images when sending to the FTP server. You can use up to 10 alphanumeric characters, - (hyphen) and _ (underscore) for naming.

Suffix

Select a suffix to add to the file name.

Date & time: The date & time suffix is added to the Image file name.

The date/time suffix consists of lower two-digits of year (2 digits), month (2 digits), date (2 digits), hour (2 digits), minute (2 digits) and second (2 digits), and consecutive number (2 digits), thus 14-digit number is added to the file name.

Sequence number: A consecutive number of 10 digits between 000000001 and 4294967295 and an consecutive 2 digits number is added to the Image file name.

Tip

A consecutive number added to **Date & time** and **Sequence number** is used to identify each of multiple files created with one alarm event.

Sequence number clear

Click **Clear** to reset the Sequence number suffix to 1.

Alarm

Select the connected alarm.

Sensor input1: The external sensor which is connected to sensor input1 of the camera I/O port.

Sensor input2: The external sensor which is connected to sensor input2 of the camera I/O port.

Motion detection: Click **Motion detection** button, and the Motion detection setting menu is displayed. You can set the motion detection function (page 61).

Note

Motion detection works only when the Video mode is set to **MPEG4** and the **Cropping** is set to **Off**.

Effective period

Set the period when the alarm detection is effective. **Always:** The alarm detection is always effective.

Schedule: You can specify the period when the alarm detection is effective in the schedule setting in the other section.

Click **Schedule** and the setting menu for the Effective period is displayed. ("Setting the Schedule — Schedule setting Menu" on page 59)

Alarm buffer

Select **Use alarm buffer** when you forward the image/ audio of before and after the alarm detection (pre-alarm, post-alarm).

If you do not select it, only the image of the moment of the alarm detection is forwarded.

Click **Alarm buffer** to display the Alarm buffer setting menu.


For details, see "Setting the Alarm Buffer — Alarm buffer setting Menu" on page 60.

OK/Cancel

See "Buttons common to every setting menu" on page 29.

Periodical sending Tab — Setting the Periodical FTP Client Activity

You can set to send an image file to FTP server periodically.



Periodical sending

Select **On** when you want to use periodical sending. If you select **Off**, Periodical sending is not executed.

Remote path

Type the remote path up to 64 characters.

Image file name

Type the file name of the image sent to FTP server up to 10 alphanumeric characters, - (hyphen) and _ (under score).

Note

You cannot send the audio file by using the periodical sending function of FTP.

Suffix

Select a suffix to be added to the file name sent to FTP server.

None: The name of the sent file will be the Image file name.

Date & time: The date & time suffix is added to the Image file name.

The date & time suffix consists of lower two-digits of year (2 digits), month (2 digits), date (2 digits), hour

(2 digits), minute (2 digits) and second (2 digits), and consecutive number (2 digits), thus 14-digit number is added to the file name.

Sequence number: A consecutive number of 10 digits between 0000000001 and 4294967295 and two fixed digits 00 is added to the Image file name.

Sequence number clear

Click **Clear** and the suffix of the sequence number returns to 1.

Mode

Select either Periodical sending mode by the timer management or Synchronized tour mode which sends in each setting position during Tour.

When you select Periodical sending mode, set **Interval** and **Effective period**.

Interval

Type the interval at which you want to send images to the FTP server periodically. You can set the hour (H), minutes (M) and seconds (S) between 1 second and 24 hours (one day).

Note

The actual interval may be longer than the set value, depending on the image size, image quality setting, bit rate and the network environments.

Effective period

Set the period when the periodical sending is effective. **Always:** The periodical sending is always effective.

Schedule: You can specify the period when the periodical sending is effective in the schedule setting in the other section.

Click **Schedule** and the setting menu for the effective period is displayed. ("Setting the Schedule — Schedule setting Menu" on page 59)

OK/Cancel

See "Buttons common to every setting menu" on page 29.



Recording Images in Memory

— Image memory setting Menu

When you click **Image memory** on the Advanced mode menu, the Image memory setting menu appears. By using the image memory function, you can record the image and audio file, which has been shot being linked with the external sensor input or with the built-in motion detection function, to the built-in memory (about 8 MB) of the camera or CF memory card. The image file can also be recorded periodically.

You can also record a still image periodically. The recorded image and audio files can be found or downloaded to the computer using the FTP server function. (See "Sending an Image via mail — e-Mail (SMTP) setting Menu" on page 46.)

Image memory setting menu is composed of three tabs Common, Alarm recording and Periodical recording.

Notes

- The image and audio files recorded in the built-in memory will be erased when the power of the camera is turned off.
- The frame rate and operability on the main viewer may decrease during image storage in the memory.
- When you remove the CF memory card or you turn off the camera with the CF memory card inside, set Easy memory function to OFF.
- Format the CF memory card in the computer before use

Common Tab — Setting the Image memory Function




Image memory

Set whether you use the Image memory function or not. When you select **On**, the Common setting options are

displays in the below. If you do not use it, select **Off** and click **OK**.

Built-in memory

It displays the free spaces of the built-in memory you can write in at present.

A-slot

It displays the free spaces of the CF memory card you can write in at present.

Selected root directory

Select a memory in which you want to save an image. **Built-in memory:** built-in memory of this camera (approximately 8 MB)

A-slot: CF memory card inserted into the slot in the front side of the camera

Overwrite

Select to overwrite the file or not when there is insufficient memory space to record the image.

Capacity warning

Select **On** to send a warning mail to the Administrator when the built-in memory space is low or the memory is full. Select **Off** if you do not want to send a warning mail.

Note

When the Overwrite is set to **On**, a warning mail is not sent to the Administrator.

SMTP server name

Type the name of the SMTP server you want to use for sending the warning mail, up to 64 characters.

Otherwise type the IP address of SMTP mail server.

Authentication

Select the authentication required when you send an alarm mail.

Off: Select if no authentication is necessary when an email is sent.

On: When authentication is necessary an e-mail is sent, select one of the authentication methods from the followings.

SMTP: Select if authentication is necessary when an e-mail is sent.

POP before SMTP: Select when POP before SMTP authentication is necessary when an e-mail is sent.

Note

When you set to **On**, be sure to select either or both **SMTP** or/and **POP before SMTP**.

POP server name

This is necessary when **POP before SMTP** is selected in **Authentication**.

Type POP (receiving mail) server name up to 64 characters. Otherwise type the IP address of POP server. This setting is necessary when SMTP server that sends a mail authenticates using the account of POP user.

User name, password

Type the user name and the password of the user who has the mail account. This setting is necessary when SMTP server that sends a mail authenticates.

Administrator e-mail address


Type the E-mail address of the recipient of the warning mail (E-mail address of the camera Administrator), up to 64 characters.

OK/Cancel

See "Buttons common to every setting menu" on page 29

Alarm recording Tab — Setting the Image Memory Function when Detecting the Alarm

You can set to record the image and audio file to the memory linked with the external sensor input or with the built-in motion detection function.



Alarm recording

Select **On** to set to record the image and audio file to the memory linked with the external sensor input or with the built-in motion detection function.

Image file name

Type the file name you want to assign to the images when saving in the built-in memory. You can use up to 10 alphanumeric characters, - (hyphen) and _ (underscore) for naming.

Suffix

Select a suffix to add to the file name.

Date & time: The Date & time suffix is added to the Image file name.

The Date & time suffix consists of lower two-digits of year (2 digits), month (2 digits), date (2 digits), hour (2 digits), minute (2 digits), second (2 digits) and consecutive number (2 digits), thus 14-digit number is added to the file name.

Sequence number: A consecutive number of 10 digits between 0000000001 and 4294967295 and an consecutive 2 digits number is added to the Image file name.

Tip

A consecutive number added to **Date & time** and **Sequence number** is used to identify each of multiple files created with one alarm event.

Sequence number clear

Click **Clear** to reset the Sequence number suffix to 1.

Alarm

Select the connected alarm.

Sensor input1: The external sensor which is connected to sensor input1 of the camera I/O port.

Sensor input2: The external sensor which is connected to sensor input2 of the camera I/O port.

Motion detection: Click **Motion detection** button, and the Motion detection setting page is displayed. You can set the motion detection function (page 53).

Notes

- **Motion detection** works only when the Video mode is set to **MPEG4** and the **Cropping** is set to **Off**.
- In the case that the synchronized preset position is specified, the alarm event that happens during moving to the preset position will be invalid.

Effective period

Set the period when the alarm detection is effective. **Always:** The alarm detection is always effective. **Schedule:** You can specify the period when the alarm detection is effective in the schedule setting in the other section.

Click **Schedule** and the setting menu for the effective period is displayed. ("Setting the Schedule — Schedule setting Menu" on page 59)

Alarm buffer

Select **Use alarm buffer** when you forward the image/ audio of before and after the alarm detection (pre-alarm, post-alarm).

If you do not select it, only the image of the moment of the alarm detection is forwarded.

Click **Alarm buffer** to display the Alarm buffer setting menu.


For details, see "Setting the Alarm Buffer — Alarm buffer setting Menu" on page 60.

OK/Cancel

See "Buttons common to every setting menu" on page 29.

Periodical recording Tab — Setting the Periodical recording mode

You can set to record the image file to the memory periodically.



Periodical recording

Select **On** when you want to use periodical recording. If you select **Off**, the Periodical recording is not executed.

Image file name

Type the file name of the image recorded to the memory up to 10 alphanumeric, - (hyphen) and _ (under score).

Note

You cannot send the audio file by using the periodical recording function.

Suffix

Select a suffix to add to the file name.

None: The recording file name will be the Image file name.

Date & time: The date & time suffix is added to the Image file name.

The date/time suffix consists of lower two-digits of year (2 digits), month (2 digits), date (2 digits), hour (2 digits), minute (2 digits), second (2 digits), and consecutive number (2 digits), thus 14-digit number is added to the file name.

Sequence number: A consecutive number of 10 digits between 0000000001 and 4294967295 and two fixed digits 00 is added to the Image file name.

Sequence number clear

Click **Clear** and the suffix of the sequence number returns to 1.

Mode

Select either **Periodical sending mode** by the timer management or **Synchronized tour mode** which sends in each setting position during Tour. When you select Periodical sending mode, set **Interval** and **Effective period**.

Interval

Type the interval at which you want to record an image in the memory periodically. You can set the hour (H), minutes (M) and seconds (S) between 1 second and 24 hours (one day).

Note

The actual interval may be longer than the set value, depending on the image size or the network environments.

Efective period

Set the period when the periodical recording is effective. **Always:** The periodical recording is always effective. **Schedule:** You can specify the period when the periodical recording is effective in the schedule setting in the other section.


Click **Schedule** and the setting menu for the effective period is displayed. ("Setting the Schedule — Schedule setting Menu" on page 59)

OK/Cancel

See "Buttons common to every setting menu" on page 29.

Directory Structure of Image Memory

The images are recorded in the memory with the following directory structure.



A _____ represents a directory created automatically. The Date_No. directory has a 11-digit name consisting of the last two digits of year (2 digits), month (2 digits), day (2 digits) underscore and sequence number (2 digits).

A directory can contain video files of up to approximately 1 MB when you use the built-in memory. A new directory will be created automatically if the size of the video files in the current directory exceeds the maximum size, and recording will continue.

Note

When you use CF memory card, the directory size varies by the card capacity.

About the extension of a file

A file to be recorded/sent using the image memory function or the FTP client function has one of the following three extensions depending on the video mode setting and the recording/sending settings of the camera.

.m4f: Represents the MPEG4 video mode.


.jpf: Represents the JPEG video mode when Use alarm buffer is checked in the alarm recording/alarm sending menu. This file includes audio data.

.jpg: Represents the JPEG video mode when Use alarm buffer is not checked in the alarm recording/ alarm sending menu. This file can be viewed with a normal image viewer.

The SNC video player (page 70) allows playing of ".m4f" and ".jpf" files.

Downloading Images from the Camera — FTP server setting Menu

When you click **FTP server** on the Administrator menu, the FTP server setting menu appears. Use this menu to set up for the FTP server function which finds a specified image and audio file stored in the built-in memory of the camera (about 8 MB) or CF memory card, or download the still image file from the camera.



FTP server function

To activate the FTP server function, select **On** and click **OK**.

When you do not use the FTP server function, select **Off** and click **OK**.

Built-in memory

It displays the free spaces of the built-in memory you can write in at present.

A-slot

It displays the free spaces of the CF memory card you can write in at present.

Selected root directory

Select the memory, which contains the file you want to download.

Built-in memory: built-in memory of this camera (approximately 8 MB)

A-slot: CF memory card inserted into the slot in the front side of the camera

OK/Cancel

See "Buttons common to every setting menu" on page 29.

Note


Note the followings when you log in the FTP server of the camera using the FTP client software of the computer.

- The frame rate and the operativity of the monitor window in the main viewer will degrade.
- While recording the image using the Image memory function, you cannot delete the recording directory.
- When the recorded image or audio file is deleted, the camera counts the free space of the built-in memory again at logging off.

Setting the Alarm Output — Alarm output setting Menu

When you click **Alarm output** on the Administrator menu, the Alarm output setting menu appears. You can set in this menu to control the alarm out of I/O port on the rear of the camera linked to the alarm detection, the timer and the Dya/Night function.

Alarm output 1, 2 Tab



Alarm output

To activate the Alarm output function, select **On**. The basic setting options are displayed below. When you do not use the Alarm output function, select **Off**.

Mode

Select the mode of the Alarm output function.

Alarm: Controls alarm output by synchronizing with an external sensor input or the built-in activity detection function

Timer: Controls alarm output by the timer.

Day/Night: Controls the alarm output linked to the day/ night function.

Alarm

This item is displayed when **Mode** is set to **Alarm**. Select the alarm to link the alarm output function. If the selected alarm is detected, the alarm output status changes.

Sensor input1: The external sensor which is connected to sensor input1 of the camera I/O port.

Sensor input2: The external sensor which is connected to sensor input2 of the camera I/O port.

Motion detection: To set the motion detection function, click **Motion detection**. The Motion detection setting page appears (see page 61).

Notes

- The motion detection function can activate or be set only when the Video mode of the camera is set to MPEG4 and the Cropping is set Off.
- In the case that the synchronized preset position is specified, the alarm event that happens during moving to the preset position will be invalid.

Alarm duration

Select the duration for which the alarm output is short-circuited between 1 and 60 sec.


Effective period

This item is displayed when **Mode** is set to **Alarm**. Set the period while the alarm detection is effective. **Always:** The alarm detection is always effective. **Schedule:** You can specify the period when the alarm detection is effective in the schedule setting in the other section.

Click **Schedule** and the setting menu for the effective period is displayed. ("Setting the Schedule — Schedule setting Menu" on page 59)

Schedule

This item is displayed when **Mode** is set to **Timer**. Click **Schedule** and the setting menu for the effective period is displayed. ("Setting the Schedule — Schedule setting Menu" on page 59)



OK/Cancel

See "Buttons common to every setting menu" on page 29.

Setting the Operations from the Viewer Page — Trigger setting Menu

Click **Trigger** on the Administrator menu to display the Trigger Setting menu.

You can set the activities of when you click Trigger icon of the main viewer in this menu.



e-Mail (SMTP)

After checking it, you will be able to select **e-Mail** in the Trigger setting menu. You can send mail with attached image file by selecting **e-Mail** and clicking the Trigger icon

When you click **e-Mail (SMTP)** button, the **Trigger (e-Mail) setting** menu is displayed. You can set necessary options here. The setting options and setting procedures are the same as those of the e-Mail (SMTP) setting menu (page 46).

Note

While the Video mode is set to **MPEG4**, the image of the composite video signal output from the video output connector of the camera may be distorted during mail transmission.



FTP client

After checking this, you will be able to select **FTP client** in the Trigger setting menu. You can send an image file to FTP server by selecting **FTP** and clicking the Trigger icon.

When you click **FTP client** button, the **Trigger (setting) FTP client** menu is displayed. You can set necessary options here. The setting options and setting procedures are the same as those of the FTP client setting menu (page 49).




Image memory

After checking this, you will be able to select **Image memory** in the Trigger setting menu. You can record an image file to the built-in memory by selecting **Image memory** and clicking the Trigger icon.

When you click **Image memory** button, the **Trigger** (setting) **Image memory** menu is displayed. You can set necessary options here. The setting options and setting procedures are the same as those of the Image Memory setting menu (page 52).




Alarm output1, 2

After checking this, you will be able to select **Alarm output1** or **Alarm output2** in the Trigger setting menu. You can control On (short circuit) or Off (open) by selecting **Alarm output1** or **Alarm output2** and clicking the Trigger icon.

Day/Night

After checking it, you will be able to select day/night in the Trigger setting menu. You can control **On** (night mode) or **Off** (day mode) of the day/night function by clicking the Trigger icon.

When you click the day/night button, the day/night setting (Trigger) menu is displayed. You can set the necessary options here. The setting options and setting procedures are the same as those of the Camera setting menu (page 34).



Note

The day/night function is invalid when its mode is set to **Disable** or **Auto** in the day/night tab even when you select day/night in the Trigger setting menu.

OK/Cancel

See "Buttons common to every setting menu" on page 29.

Setting the Schedule

Schedule setting Menu

When you click **Schedule** on the Administrator menu, the Schedule setting menu appears.

This is the same menu as the setting menu which is displayed when you click **Schedule** to set Effective period and Schedule in FTP client setting menu, e-Mail (SMTP) setting menu, Image memory setting menu, Alarm out setting menu, Day/Night setting Tab and so on.

Example: When setting e-Mail (SMTP) (the alarm sending) in the Schedule setting menu



Schedule selection

Select the list box to specify the schedule you want to set. e-Mail (SMTP) – Alarm, e-Mail (SMTP) – Periodical, FTP – Alarm, FTP – Periodical, Image memory – Alarm, Image memory – Periodical, Alarm output1 – Alarm, Alarm output1 – Timer, Alarm output2 – Alarm, Alarm output2 – Timer or Day/Night – Timer can be selected.

The time period on the right of the checked day is the effective period of the schedule.

Mon (Monday) to Sun (Sunday)

The time period on the right of the checked day is the effective period of the schedule.

Start time, Stop time

Specify the Start time and the Stop time.

Use the same time schedule every day


When this is checked, the Start time and Stop time set to **Mon** (Monday) are applied to all days. In this case, the Start time and Stop time of the other days than **Mon** (Monday) cannot be input.

OK/Cancel

See "Buttons common to every setting menu" on page 29.

Setting the Alarm Buffer — Alarm buffer setting Menu

When you click **Alarm buffer** on the Administrator menu, the Alarm buffer Setting menu appears. You can set the Pre-alarm image and audio (the image and audio before the alarm detection) and the Post - alarm image and audio. These can be set when **Alarm sending** or **Alarm recording** of FTP client setting menu or Image memory setting menu is set to **On**, and besides when **Use alarm buffer** is selected.



Video mode

The Video mode set in the Common tab of the Camera setting menu is displayed.

MPEG4: Shows the present output format of the camera is MPEG4

JPEG: Shows the present output format of the camera is JPEG.

Recording capacity

Displays the maximum recording capacity of alarm buffer in the present camera setting of the video mode, image size, bit rate and frame rate.

Pre-alarm period: Displays the maximum recording capacity of image/audio before the alarm detection.

Post-alarm period: Displays the maximum recording capacity of image/audio after the alarm detection.

Recording time

Set the recording time for the Pre-alarm image/audio and Post alarm image/audio.

Pre alarm period: Type the recording time of the image/audio before the alarm detection.

Post alarm period: Type the recording time of the image/audio after the alarm detection.

Note

The value of Recording capacity differs depending on Image size, Bit rate (for MPEG4) and Image quality (for JPEG) in the camera setting menu.

OK/Cancel

See "Buttons common to every setting menu" on page 29.

Setting the Motion Detection Function — Motion detection setting Menu

When you click **Motion detection** on the Administrator menu, the Motion detection setting menu appears. You can set the conditions to activate the built-in motion detection function in this menu.

This is the same menu with the setting menu which is displayed when you click **Motion detection** in Alarm sending of e-Mail (SMTP) setting menu, Alarm sending or FTP client setting menu, Alarm recording of Image memory setting menu and so on.

Note

The motion detection function can activate or be set only when the Video mode of the camera is set to **MPEG4** and the **Cropping** is set **Off**.



The Motion detection setting menu is composed of the following five parts.

Monitor display

You can monitor the moving image and sets the detection Window.

Window 1 to 4 check box

When you check it, the specified Window is displayed on the monitor display.

Threshold slider bar

Set the Threshold level so as to judge whether there has been any motion in the camera image or not. You can change the Threshold level displayed in the Motion detection indicator.

Motion detection indicator

The moving level of the present shooting image inside the specified Window is shown in the graph. The even line shows the threshold level for Motion detection which will be a guide to set the sensitivity properly.

Sensitivity slider bar

Use it to set the sensitivity of the monitoring image. When the slider bar is moved to the left end, the sensitivity will be 0 and any motion will not be detected. The right end is the maximum sensitivity.

Setting the Motion Detection Area, Sensitivity and Threshold level

Set the motion detection working area, the sensitivity and the threshold level as follows:

- 1 Check Window 1 check box. Window 1 is shown on the monitor display.
- 2 Settle Window 1 in the area you want to set Motion detection.
 Click and drag Window 1 to move it or change the size of it.
- Set the Sensitivity of Motion detection.
 Adjust it referring to the level indicator of Motion detection.
 To increase the sensitivity, move the Sensitivity slider bar to the right.
 To decrease, move it to the left.
 When you release the mouse, the new setting is applied to the level of motion detection indicator.
- 4 Set the Threshold level of Motion detection.
 Adjust the Threshold slider bar in the same way of step 3 to set the level the camera executes motion detection.
- If necessary, set the Motion detection working areas, the sensitivities and the Threshold level of the other Windows 2, 3, 4 by following steps 1 to 4.
- **6** After all settings, click **OK**.

Notes

- While motion detection setting menu is displayed, motion detection of e-Mail (SMTP), FTP client, Image memory and Alarm output notification will not work. Make sure to close Motion detection setting menu after setting.
- Before using the Motion detection, perform the operation test to confirm correct operation.

- The Motion detection may not operate correctly in the following cases:
 - while changing a setting on the Camera setting menu
 - when the object is dark
 - when the camera is installed in an unstable place that causes vibration to the camera
 - when a small bit rate (64 kbps, 128kbps) is selected in **Bit rate** setting of MPEG4

Saving the Camera Position and Action — Preset position setting Menu

When you click **Preset Position** of the administrator setting menu, the preset position setting menu is displayed. In this menu, PanTilt and Zoom position can be saved and you can set a Tour (program).

Position tab — Saving PanTilt and Zoom position

The camera can save up to 16 items, PanTilt or Zoom for example.



Preset No.

Select a preset number from 1 to 16 in the list box.

Preset position name

Write the preset position name of the selected preset number.

Recall: When you click **Recall**, the camera moves to the position of the selected preset number at present.

Set: Use it to save the camera position to a preset number.

Carry out the following steps.

- Move the camera to the position to be saved while you are checking the image with the main viewer.
- 2 Select a preset number for saving, and write the preset position name.
- 3 Click the registration button. The camera position is saved.

Reset: When you press **Reset**, deletes the saved contents of the current selected preset number.

Position at alarm

The camera can synchronize the preset position with Sensor input 1 or 2 or with the activity detection function.

If an alarm is detected by the sensor input or the activity detection function, the camera automatically moves to the corresponding preset position.

Sensor input1: Select a preset position to synchronize with the alarm from Sensor 1.

Sensor input2: Select a preset position to synchronize with the alarm from Sensor 2.

Motion detection: Select a preset position to synchronize with the alarm from the motion detection.

In the case not to synchronize with any preset number, select **None**.

Note

In the case that the synchronized preset position is specified, the alarm event that happens during moving to the preset position will be invalid.

List of the preset positions

When you click **Reset position table**, displays each preset number and its name on the another window.



Tour Tab — Setting a Tour

Up to 16 positions can be programmed, and the camera moves to the programmed positions sequentially (Tour). Up to 5 groups can be set as the Tour.



Tour name

Select a tour name from among A, B, C, D and E.

Stay time

Type a period of time for which the camera is to stay at each preset position, between 1 and 3600 seconds.

Speed

Select the Pan speed from the list box. The camera pans faster with a higher number setting.

Sequence

Select and set preset number 1 to 16 for each of 16 list boxes.

The camera moves to the preset position saved in the selected preset number sequentially. The sequence of camera movement starts from the preset position specified in the list boxes from left to the right, then from top to bottom. After bottom right, the camera returns to top left. This sequence is cyclical.

If you select **End** in the list box, the program ends before this and the camera returns to the first preset position. This sequence is cyclical.

Tour table

You can check the contents of Tour settings on the another window.



Tour selection

You can activate the tour according to the schedule.

Selected tour name

Select the tour name **A** to **E** you want to activate. Select **None** if you do not want to activate any tour or if you want to stop the tour in action.

Effective period

Select the period for which the tour activates. **Always:** The tour can be activated any time. **Use scheduler:** The tour is activated according to the schedule you have set.

Resume time on inactivity

You can operate PanTilt or Zoom during the tour, or select the tour activity after the preset activity by the alarm.


On: Specify the wait time before the tour restarts, between 5 and 600 seconds. The tour restarts automatically after the specified time has elapsed.

Off: The tour does not restart. None is displayed on Selected tour name.

Transmitting with External Equipment Using the External Serial Terminal — Serial setting Menu

When you click **Serial** of the administrator setting menu, Serial setting menu is displayed.

In this menu, you can input data into the camera from the computer via a network and output them to the external serial interface, and control a peripheral device. You can input data from a peripheral device via an external serial interface and output them to the computer via a network.



Mode

Select a mode from TCP port or the camera control with VISCA protocol for transmitting data via a network.

TCP: When you select TCP, input and output data through the external serial transmission port can be sent and received by specifying the port number in TCP port number. You can check easily by DOS command "telnet host name port number".

VISCA: Select it when you control the camera with VISCA protocol. As for the command list of VISCA protocol, refer to the dealer of your camera or Sony Commercial Products Service Counter nearby.

Notes

- When you execute serial control with VISCA protocol, match the transmission setting with the connected controller.
- This camera does not correspond to the daisy chain connection of VISCA device. Use the camera and the controller one-on-one.

TCP port No.

When "TCP" is selected in the mode, input the port number corresponding to TCP port. Use other than Well-Known port numbers (0 to 1023).

Baud rate

Select a baud rate which corresponds to the peripheral device of serial interface. Selectable baud rates are shown below.

38400, 19200, 9600, 4800, 2400, 1200, 600, 300 (bps)

Parity bit

Select a parity which corresponds to the peripheral device of serial interface from among **None**, **Odd** or **Even**

Character length

Select the character length which corresponds to the peripheral device of serial interface from 7 or 8 (bits).

Stop bit

Select the stop bit which corresponds to the peripheral device of serial interface from 1 or 2 (bits).

Others

This section explains how to use the application software and commands, including the supplied CD-ROM.

Using the Supplied Setup Program

Explains the functions except the Network tab in the Setup Program.

To install the Setup Program, to assign the IP address and to set the network, see "Assigning the IP address to the Camera" on page 9 in "Preparations".

Starting the Setup Program

Select **Program** from Start menu of Windows, then select **Program**, **IP Setup Program** and **IP Setup Program** in sequence.

The IP Setup Program starts.

Network tab appears. The IP Setup Program detects cameras connected to the local network and lists them on the Network tab window.


Bandwidth Control Tab

The communication bandwidth can be set when the Video mode of the camera is set to **JPEG**.

Note

When the Video mode of the camera is set to **MPEG4**, the bandwidth cannot be changed.

Click the Bandwidth control tab to display the bandwidth setting window. The current bandwidth is displayed in Current bandwidth.




- **2** Click to select the camera to set the bandwidth from the list box.
- 3 Click to select the desired bandwidth from the **Setting bandwidth** list box.
- Type the Administrator name and Administrator password in each box.
- **5** Click **OK**. If "Setting OK" is displayed, the bandwidth setting is completed.

Othe

Date time Tab

You can set the date and time on the camera.

1 Click the Date time tab to display the date/time setting window.



2 Click to select the camera you want to set the date and time for.

You can select multiple cameras and set the date and time simultaneously.

- 3 Select the date/time format from the **Date time format** drop-down list.
- 4 Select the area where the camera is installed from the **Time zone selecting** drop-down list.
- **5** Set the date and time.

You can set the date and time in two ways.

Manual current date time setting

Set the current date and time on the **Manual** current date time setting boxes, and click **OK**. The setting boxes are for the year (last two digits), month, date, hour, minutes and seconds from left to right.

PC current date time setting

The date and time set on the computer is displayed in the **PC current date time setting** box.

Click **OK** on the right to set the camera's date and time to the displayed computer's date and time.

Note


Due to network properties, there may be a slight difference between the displayed computer's date and time and those set on the camera.

PPPoE Tab

PPPoE is used to connect to an ISP (Internet Service Provider) via the Internet. Using PPPoE, you can automatically obtain an IP address to connect to the Internet from the ISP.

The following PPPoE setting items are provided for the SNC-RZ25N/RZ25P.

- User ID assigned by your ISP
- · Password for the user ID
- DNS setting (automatic/manual setting)
- 1 Click the PPPoE tab to display the PPPoE setting window.



- **2** Click to select the camera you want to make the PPPoE settings for.
- Select On below the list to enable the PPPoE setting.To disable the PPPoE setting, select Off.
- 4 Type the user ID assigned by the ISP in the **User ID** box.
- 5 Type the password for the user ID in the **Password** box.

- Retype the password for the user ID in the **Re-type** password box.
- **7** Set the DNS server address.

To obtain the DNS server addresses automatically:

Select Obtain DNS server address automatically.

To specify the DNS server addresses manually: Select Use the following DNS server address, and type the Primary DNS server address and Secondary DNS server address in each box.

- 8 Type the Administrator name and Administrator password in each box.
- **9** Click **OK**. If "Setting OK" is displayed, the PPPoE setting is completed.

Rebooting the Camera

Click **Reboot** on the Network tab to reboot the camera. It will take about two minutes to start again.

Using the SNC audio upload tool — Transmitting Audio to Camera

The supplied SNC audio upload tool allows you to transmit sound from the computer to the camera. This section explains the setup and operations of the SNC audio upload tool.

The SNC audio upload tool supports the following audio data to be transmitted.

Audio CODEC	Transmission rate
G711 (μ-LAW)	64 kbps
G.726	40 kbps
G.726	32 kbps
G.726	24 kbps
G.726	16 kbps

Note

Only one administrator can transmit sound to the camera. Meanwhile, other user with adoministrator ID and a password will not be able to transmit sound to the camera.

Installing the SNC audio upload tool

- Insert the supplied CD-ROM disc into your computer CD-ROM drive.
 After a short time a window will open displaying the files on the CD-ROM.
- **2** Click the **Setup** icon of **SNC** audio upload tool. The "File Download" dialog opens.
- 3 Click Open.

Note

If you click "Save this program to disk" on the "File Download" dialog, you cannot install correctly. Delete the downloaded file, and click Setup icon again.

Install the SNC audio upload tool following the wizard displayed.
If the Software License Agreement is displayed, read it carefully and accept the agreement to continue the installation.

Connecting the Camera to the Computer

- **1** Connect a speaker to the ♥ (line output) jack on the camera.
- Connect a microphone to the microphone input jack on the computer.

Note

If the microphone input jack of the computer is not set correctly, no sound is transmitted from the computer and nothing is output from the speaker connected to the camera.

Set the microphone input jack from the control panel of Windows.

On Windows 2000

- 1 Select Sounds and Multimedia from Control Panel.
- 2 Click Volume in the Sound Recording section on the Audio tab.
 The Recording Control window opens
- **3** Check **Select** in the **Microphone** section.


On Windows XP

- 1 Select Sounds and Audio Device from Control Panel.
- 2 Click Volume in the Sound Recording section on the Audio tab. The Recording Control window opens.
- **3** Check **Select** in the **Microphone** section.

Using the SNC audio upload tool

When you start the SNC Audio Upload Tool, the following window is displayed.

Menu tab



➤ (start)/■(stop)

Click ► (start) to start sound transmission. The transmission speed is displayed in the Bitrate box during transmission. You can adjust the microphone volume and enable/disable the muting, if necessary.

To stop the sound transmission, click ■(stop).

Note

If you change **Proxy IP Address, Proxy Port, CODEC** on the Setting tab during the sound transmission, the changed settings will be effective after the transmission.

Sound adjustment and indicators

Adjust the microphone input volume by moving the slider bar. You can adjust the volume even during the transmission.

Click the microphone icon to enable/disenable the sound muting.

The transmission rate is displayed in the Bitrate box. The microphone input volume is displayed at the Level.

=

Setting tab



User

Set the **User ID** and **Password** for the administrator. The default setting of the User ID for the Administrator is "admin," and the Password is "admin."

Camera address

Type the IP address or host name of the camera you want to transmit sound.

Camera port

Set the port of the camera you want to transmit sound. The default port is "HTTP" (80).

CODEC

Select the audio mode (CODEC) from the drop-down list

Using the SNC video player — Playing Video/ Audio File Recorded on Camera

The supplied SNC video player allows you to play video/audio data recorded on the camera with your computer.

This section explains the setup and operations of the SNC video player.

Downloading the SNC video player

To download the SNC video player, click the Player icon located on the upper part of the main viewer of the camera.

Input the Administrator name and Administrator password on the download dialog.

Note

To operate the SNC video player, a special DLL file is necessary. This file is automatically installed in the computer when you view camera images with the ActiveX viewer.

Using the SNC video player

1 Double-click the SNC video player downloaded from the camera to start this application.



- 2 Click the icon.
 The Select File dialog opens.
- **3** Select the file you want to play.

Information boxes on the selected file are displayed on the left side of the window as follows:

Each click on the (information) icon switches between "display" and "Not to display" of the file information.

Model name: Model name of the camera with which the file is recorded.

IP address: IP address of the camera with which the file is recorded.

Serial number: Serial number of the camera with which the file is recorded.

Record event: Type of event used for the recording: **Sensor input, Periodical, Motion detection** or **Manual**.

Date&time: Recording date and time

Movie: Video CODEC Audio: Audio CODEC

Playing a video/audio file

Click (start) to start playing from the beginning of the selected file.

To freeze the movie temporarily, click (pause).

Click again to restart playing. To stop playing, click (stop).

To restart playing, click (start) again.

Play stops when the file is played to the end.

To play from a specified point

Move the slider bar below the image display, and playing starts according to the slider bar position.

Adjusting the sound

Adjust the playing sound volume by moving the slider bar. Move it to the left end for the minimum volume, and to the right end for the maximum volume.

Click the speaker icon to enable/disable the sound muting.

When the sound muting is on, no sound is heard even if you move the slider bar to the right.

Saving an image

Click (capture) icon during playing or pause and the captured image is displayed on a pop-up dialog. To save the image, click **Save** on the dialog. You can specify the destination to which the image is to be stored and select the JPEG or Bitmap format.

Using the SNC panorama creator — Creating a Panorama Image

The supplied **SNC panorama creator** allows you to create a panorama image to be displayed on the main viewer.

Using the panorama image, you can move the camera to the desired position simply by clicking on the image. This section explains the setup and operations of the SNC panorama creator.

Installing the SNC panorama creator

- Insert the supplied CD-ROM disc into your computer CD-ROM drive.
 After a short time a window will open displaying the files on the CD-ROM.
- **2** Click the **Setup** icon of **SNC panorama creator**. The "File Download" dialog opens.
- 3 Click Open.

Note


If you click "Save this program to disk" on the "File Download" dialog, you cannot install correctly. Delete the downloaded file, and click the Setup icon again.

4 Install the SNC panorama creator following the wizard displayed.
If the Software License Agreement is displayed, read it carefully and accept the agreement to continue installation.

Using the SNC panorama creator

When you start the SNC panorama creator, the following window is displayed.

The window consists of a main section to create a panorama image and a setting section to prepare for connection to the camera.



The created panorama image is displayed in the upper viewer.

Angle setting

Set the view angle within the created 360-degree panorama image.

Select the angle (degrees) from among "90," "180," "270" or "360."

If you want to limit the camera movement to the selected view angle, check the "Lock" check box. The camera moves only within the selected panorama view angle.

Note

The edges of the panorama image may not be displayed correctly when the camera is zoomed in.

Make: Starts shooting for creating a panorama image (a complete 360-degree panorama image). It takes about two minutes to create a complete panorama image.

Note


The exposure and white balance settings are fixed while a panorama image is being created. To create a clear panorama image, set **Exposure mode** to **Full auto** and **White balance** to **Auto** in the Camera setting menu and point the camera to the main subject before starting shooting.

File-open: Allows use of a Bitmap or JPEG image file in spite of a panorama image.

Note

The size of the image in the file should be 320×90 pixels (horizontal/vertical). Other image sizes are not supported.

Send: Transmits a panorama image converted into a JPEG file to the camera.



Administrator name: Type the ID of the administrator of the camera.

Administrator password: Type the password of the administrator of the camera.

Camera address: Type the IP address or host name of the camera.

Camera port No.: Type the port number of the camera. **Use proxy:** Check this item when you use a proxy server.

Proxy server name: Type the IP address or host name of the proxy server.

Proxy server port No.: Type the port number of the proxy server.

Preparing connection to the camera

Before creating a panorama image, set the following items in the Setting section to allow connection to the camera

Administrator name: Type the ID of the administrator of the camera to be connected.

Administrator password: Type the password of the administrator of the camera to be connected.

Note

The default settings of both items are "admin."

Camera address: Type the IP address or host name of the camera to be connected.

Camera port No.: Type the port number of the camera to be connected.

When you use a proxy server for camera connection, check the **Use proxy** check box and set the following items.

Proxy server address: Type the IP address or host name of the proxy server.

Proxy server port No.: Type the port number of the proxy server.

Preparations for connecting to the camera are now completed.

<u>_____</u>

Creating and transmitting a panorama image

1 Click the Make button to start shooting.
A panorama image will be created in about two minutes.

Note

Do not make settings of the camera or move the camera during shooting.

2 Select the view angle for a panorama image on **Angle Setting**.

To limit the pan/tilt range of the camera to the selected view angle, check the **Lock** check box.

3 Click the **Send** button to transmit the panorama image to the camera.

The panorama image is saved in the camera.

You can use the saved panorama image when you control panning and tilting from the main viewer.

Saving a custom image to the camera

You can save a custom image to the camera in spite of the panorama image shot by the camera.

Prepare the image to conform to the following requirements:

• File format: JPEG or Bitmap

• Image size: 320×90 pixels (horizontal/vertical)

The camera does not support use of images that do not conform to the above conditions.

- 1 Click the **File open** button. The File dialog opens.
- **2** Select the image you have prepared.
- 3 Select the view angle of the image to be created on **Angle setting**.

To limit the pan/tilt range of the camera to the selected view angle, check the **Lock** check box.

4 Click the **Send** button to transmit the prepared image to the camera.

The image is saved in the camera.

You can use the saved image when you control panning and tilting from the main viewer.

Tip

The panorama image is the still image converted from the image taken when you were going to create a panorama image with "SNC panorama creator". When the camera is moved or when the layout around the camera is changed, create the panorama image again.

Using the CustomHomepage Installer

You can store the homepage that you have created in the camera and watch it.

Notes on creating the homepage

When you creating the homepage, note the following points.

- The file name should be typed up to 24 characters including the extension.
- The file size of the homepage should be 2.4 MB or less.
- To watch the created homepage, set the **Default URL** in the System setting menu.


Uploading the Custom Homepage Installer to the Camera

- 1 After a short time a window will open displaying the files on the CD-ROM.
- 2 Click the Setup icon of Custom Homepage Installer.

The "File Download" dialog opens.

3 Click Open.


The installer starts and notes are displayed.




Note

If you click "Save this program to disk" on the "File Download" dialog, the

CustomHomepageInstaller.exe file will be saved on the computer. Double-click the saved file to start it. 4 Read the notes carefully, and click **Next**. The Software License Agreement is displayed.



Read the agreement carefully, select Agree if you accept it, then click Next.



- **6** Type the IP address of the camera to be uploaded in the IP address box.
- 7 Specify the HTTP port No. of the camera. Initial HTTP port No is set to 80.
- **8** When you use a proxy server, set the following: For the proxy server of your environments, consult your network administrator.

When using an HTTP proxy server:

Select **Use HTTP proxy server**, and type your settings in the Proxy server address and Proxy server port No. boxes.


When using an FTP proxy server:

Select **Use FTP proxy server**, and type your settings in the Proxy server address and Proxy server port No. boxes.

Note

If you cannot establish communication with the camera with the proxy server being used, connect the camera to the local network and run the installer without using the proxy server.

- **9** Type the Administrator name and Administrator password of the camera to be uploaded.
- **10** Confirm that all items are correct, then click **Next**.



11 Type the path for the folder in which your homepage is stored in the Source folder box, then click **Next**.




12 Click **OK**. Uploading of the homepage file starts.

Note

Do not turn off the camera until the camera is rebooted after uploading the homepage file.



The following page will appear after a while.



After displaying this page, the camera will be adjusted and rebooted automatically in two minutes.

13 Click **Finish** to exit the program.

Assigning the IP Address to the Camera Using ARP Commands

This section explains how to assign an IP address to the camera using ARP (Address Resolution Protocol) commands without using the supplied setup program.

Note

Enter the ARP commands within 5 minutes of the power of the camera being turned on.

- 1 Open the DOS window on the computer.
- **2** Enter the IP address and the MAC address of the camera to assign a new IP address, using the following ARP commands.

arp -s <Camera's IP address> <Camera's MAC address> ping -t <Camera's IP address>

Example:

arp -s 192.168.0.100 08-00-46-21-00-00 ping -t 192.168.0.100

When the following line is displayed on the DOS window, hold down **Ctrl** and press **C**.

Reply from 192.168.0.100:bytes=32 time...

You will normally receive a reply after about 5 repetitions of "Request time out."

Note

If you do not receive a reply, check the following:

- Did you enter the ARP commands within 5 minutes of the camera being turned on?
 - If not, turn off the camera and restart the operation.
- Is the NETWORK indicator on the camera flashing? If the indicator goes off, the network connection has a problem. Connect the network correctly.
- Did you enter the IP address previously used for another device?
 - Assign a new IP address to the camera.
- Do the computer and the camera have the same network address?
 - If not, set the same network address on the computer and the camera.

Using the SNMP

This unit supports SNMP (Simple Network Management Protocol). You can read MIB-2 objects and write some MIB-2 objects using software such as SNMP manager software. This unit also supports the coldStart trap which occurs when the power is turned on or the unit restarts, and the Authentication failure trap which informs of an illegal access using SNMP. Using CGI commands, you can set community name and access limitation, reading/writing right, host to send traps, and some MIB-2 objects. To allow these settings, you need authentication by the camera administrator.

1. Inquiry Commands

You can check the SNMP Agent settings using the following CGI commands.

<Method> GET, POST

<Command>

"http://ip_adr/snmpdconf/inquiry.cgi?inqjs=snmp (JavaScript parameter format) http://ip_adr/snmpdconf/inquiry.cgi?inq=snmp (standard format)

With the above inquiry, you can obtain the following setting information. The following explains the setting information using the inqjs=snmp (JavaScript parameter) format.

var sysObjectID="1.3.6.1.4.1.122.8501" var sysLocation="\"\"" var sysContact="\"\"" var sysName="\"\"" var snmpEnableAuthenTraps="1" var community="public,0.0.0.0,read,1" var community="private,192.168.0.101,write,2"	
var sysLocation="\"\""\" var sysContact="\"\""\" var sysName="\"\""\" var smpEnableAuthenTraps="1"\" var community="public,0.0.0,read,1"\" var community="private,192.168.0.101,write,2"\"	1
var sysContact="\"\""\" var sysName="\"\""\" var snmpEnableAuthenTraps="1"\" var community="public,0.0.0,read,1"\" var community="private,192.168.0.101,write,2"\"	.(2)
var sysName="\"\""\" var snmpEnableAuthenTraps="1"\" var community="public,0.0.0.0,read,1"\" var community="private,192.168.0.101,write,2"\"	.③
var smmpEnableAuthenTraps="1" var community="public,0.0.0.0,read,1" var community="private,192.168.0.101,write,2"	.4
var community="public,0.0.0.0,read,1" var community="private,192.168.0.101,write,2"	.(5)
var community="private,192.168.0.101,write,2"	.6
	$\overline{\mathcal{O}}$
	.8
var trap="public,192.168.0.101.1"	

- ① describes the case of "mib-2.system. sysDescr.0". You cannot change this parameter.
- ② describes the case of "mib-2.system. sysObjectID.0". You cannot change this parameter.
- ③ describes the case of "mib-2.system. sysLocation.0". This field is used to describe information on the location of this camera. Nothing is set at the factory.

- describes the case of "mib-2.system. sysContact.0". This field is used to describe the information on administrator of this camera. Nothing is set at the factory.
- (5) describes the case of "mib-2.system. sysName.0". This field is used to describe administration mode of this camera. Nothing is set at the factory.
- 6 describes the case of "mib-2.snmpEnable AuthenTraps.0". This example shows when "1" (enable) is set. With this setting, a trap occurs when there is an Authentication failure. When "2" (disable) is set, no Authentication failure trap occurs.
- describes the community name and the reading/ writing attributes. This example shows the identification number "ID=1", the community name public, and enables read from any IP address (0.0.0.0).
- (8) describes the community name and the reading/writing attributes, similarly to (7). This example shows the identification number ID=2, the community name "private", and enables "read/write" by the SNMP request packet from the host "192.168.0.101".
- 9 describes the host name to send a trap. This example shows the identification number "ID=1", the community name "public", and enables sending of traps to the host having the IP address "192.168.0.101".

2. Setting Commands

The unit supports the following setting commands of SNMP.

<Method>

GET, POST <Command>

http://ip_adr/snmpdconf/snmpdconf.cgi? <parameter>=<value>&<parameter>=...&...

First, perform the settings of the following parameters.

- sysLocation=<string>
 Set the case of "mib-2.system.sysLocation.0" in the <string> position. The maximum length of <string> is 255 characters.
- 2) sysContact=<string>
 Set the case of "mib-2.system.sysContact.0" in the <string> position. The maximum length of <string> is 255 characters.

- 3) sysName=<string> Set the case of "mib-2.system.sysName.0" in the <string> position. The maximum length of <string> is 255 characters.
- 4) enaAuthTraps=<value>
 Set the case value of "mib-2.snmp.snmp
 EnableAuthenTraps.0" in the <string> position.
 Type "1" (enable) or "2" (disable) in the <value>
 position.

Example: To allow reading/writing by any host in the "private" community and having the ID number "2". community=2,w,private,0.0.0.0

6) trap=<ID>,<communityName>,
 <IpAddressString>
 Set the host you want to send traps to. <ID>
 describes the setting identification number (1 to 8),
 <communityName> describes the community
 name to send traps to, and <IpAddressString>
 describes the IP address of the host to send traps to.

Example: To specify the destination of traps as the private community and the ID number "1". rap=1,public,196.168.0.101

- delcommunity=<ID>
 This parameter is used to delete the previous community setting. <ID> describes the community setting identification number (1 to 8).
- 8) deltrap=<ID>
 This parameter is used to delete the previous setting of the host to send traps to. <ID> describes the trap setting identification number (1 to 8).

When you have finished changing the SNMP setting information using the above parameters 1) to 8), check the changed settings using an inquiry commands. If the changed settings are OK, restart the SNMP using the following CGI command.

SNMP restart command

<Method>
GET, POST

<Command> http://ip_adr/snmpdconf/snmpdconf.cgi? snmpd=restart



Specifications

Network

Protocol TCP/IP, ARP, ICMP, HTTP, FTP

> (server/client), SMTP (client), DHCP (client), DNS (client), NTP (client), SNMP (MIB-2), RTP/

RTCP, PPPoE

Compression

Video compression format

MPEG4/JPEG

Audio compression format

G.711/G.726 (40,32,24,16 kbps)

 $640 \times 480 \text{ (VGA)}, 480 \times 360, 384 \times$ Image size

 $288,320 \times 240 \text{ (QVGA)}, 256 \times 192,$

 $160 \times 120 (QQVGA)$

Maximum frame rate

SNC-RZ25N

Max. 30 FPS (QVGA)

SNC-RZ25P

Max. 25 FPS (QVGA)

Internet Explorer Ver. 5.5 or 6.0 Web browser

(Available OS: Windows 2000/ XP)

Computer environments

CPU: Pentium III, 1 GHz or higher

(Pentium 4, 2 GHz or higher

recommended)

RAM: 256 MB or more

Display size: 1024×768

Maximum user access

In JPEG mode: 20 users

In MPEG4 mode: 10 users

Network security

Password (basic authentication), IP

filtering

Homepage customization

Starting from a homepage in the builtin flash memory or CF is possible.

Other functions Activity detection, image trimming,

built-in clock, etc.

Camera

Video signal SNC-RZ25N: NTSC Color

SNC-RZ25P: PAL Color

Picture element 1/4 inch color CCD

(Total picture elements:

SNC-RZ25N: Approx. 410,000 SNC-RZ25P: Approx. 470,000) (Effective picture elements: SNC-RZ25N: Approx. 380,000

SNC-RZ25P: Approx. 440,000)

18× (Optical), 12× (Digital) Lens

f=4.1 to 73.8 mm, F1.4 to F3.0

Horizontal angle: 2.7 to 48.0 degrees

Minimum object distance

 $30 \text{ mm} (1^3/_{16} \text{ inch})$:

Minimum illumination

0.7 lx (F1.4)/with 50 IRE

Shutter speed 1/1 to

1/10,000 s

Horizontal resolution

NTSC: 470 TV (WIDE end) PAL: 460 TV (WIDE end)

Video S/N 50 dB

Mechanism

Pan -170° to +170°, 340°, 100° rotation/

second

Tilt -90° to $+30^{\circ}$, 120° , 90° rotation/second

Pan/tilt action

Horizontal: ±170 degrees

Maximum speed: 100 degrees / s, Vertical: +90 degrees, -30 degrees Maximum speed: 90 degrees / s

Interface

Network port 10BASE-T/100BASE-TX (RJ-45) I/O port Sensor input : \times 2, make contact

Alarm output : \times 2, 24 V DC or less, 1

(mechanical relay outputs electrically isolated from the

camera)

Serial interface Transparency type RS-232C VIDEO OUT: BNC, 1.0 Vp-p, Video output

75 ohms, unbalanced, sync negative

CF card slot Wirless card (802.11b)

Memory card (storage)

Microphone input

Sensitivity: $-40 \pm 3.5 \text{ dB}$ Freguency range: 50-15,000Hz

plug: Ø3.5 mm (5/32 inches), Mini-plug,

plug-in power system

Type: Active speaker Line output

> Input impedance: 4.7 kohms or more plug: Ø3.5 mm (⁵/₃₂ inches), Mini-plug

Others

12 V DC ± 10% Power supply

 $24 \text{ V AC} \pm 10\%$, 50/60 Hz

Power consumption

17 W max.

Operating temperature

 $0 \,^{\circ}\text{C}$ to +40 $^{\circ}\text{C}$ (32 $^{\circ}\text{F}$ to 104 $^{\circ}\text{F}$)

Storage temperature

-20 °C to 60 °C (-4 °F to 140 °F)

Operating humidity

20 to 80 %

Storage humidity



20 to 95 %

 $200 \times 140 \times 148 \text{ mm} (7^{7}/_{8} \times 5^{5}/_{8} \times 5^{1})$ **Dimensions**

⁷/₈ inches)

not including the projecting parts, lens

and tripod adapter

Approx. 1.3 kg (2 lb 14 oz) Mass

Supplied accessories

CD-ROM (setup program and User's

Guide) (1)

Ceiling bracket (A) (1)

Ceiling bracket (B) (1)

Wire rope (1)

Screws \oplus M 3 × 6 (6)

Installation Manual (this document)

(1)

B&P Warranty Booklet (1) (SNC-

RZ25N only)

Optional accessories

Wirless card

SNCA-CFW1

Antenna for wireless card

SNCA-AN1

Memory stick Duo adapter corresponding to compact

flash(tm) slot

MSAC-MCF1

Memory stick Duo

MSX-M512S (512MB)

Design and specifications are subject to change without notice.

М Index DNS server40, 41 Dynamic IP address notification43 main viewer 11, 17 main viewer page......17 E memory......52 e-mail......29 Access log34 menu section......17 e-Mail (SMTP).....29 access right45 monitor Image19 e-Mail (SMTP) setting Menu......46 ActiveX viewer.....16 monitor image section19 E-mail address43 activity detection function......61 Motion detection......30, 61 e-mail address......43 motion detection......30, 61 Administrator 14, 44 Motion detection setting Menu......61 administrator 14, 44 F administrator menu page29 MPEG4......34, 38 Factory default......33 Alarm.....50 N factory settings33 alarm......50, 56 flash memory......31 Alarm buffer 30, 50, 60 Network 29, 40, 41 format of date and time32 alarm buffer 30, 50, 60 network......29, 40, 41 Alarm buffer setting Menu......60 network configuration40 Alarm output 26, 30, 56 Network setting Menu.....40 FTP client30, 58 alarm output 26, 30, 56 FTP client setting Menu.....49 0 Alarm output setting Menu56 FTP server30, 49 Alarm recording53 OK button......29 FTP server setting Menu55 overwrite.....52 ARP commands......75 Н P В Home18 Password......44 Homepage Custom Tool......73 Backup setting data33 password......44 HTTP......43 Bandwidth66 Periodical recording54 HTTP port number10 periodical recording.....54 C Periodical sending48, 51 periodical sending......48, 51 Image memory......25, 30 camera setting......34 Picture......36 image memory......25, 30 Camera setting Menu34 Image memory setting Menu......52 Cancel button......29 port number40 Image size......35 PPPoE......67 capture 18, 21 preset position......23 Internet Explorer11 CGI commands......76 proxy server.....44 IP Address9 communication bandwidth......66 R IP address notification......43 Cropping......35 cropping......35 Custom Homepage Installer......31 recording images52 Java applet viewer16 reset39 D JPEG......34, 38 S Date & time.......32 date and time 32, 67 saturation......37 default gateway......40, 41 loading the setting data.....33 saves the setting data.....33 Default policy......45 DHCP......40, 41 schedule......30. 59

Schedule setting Menu 59	
Security	
security29	
security setting45	
Security setting Menu45	
sending images49	
Serial number31	
serial number31	
Setting 17	
Setup Program	
sharpness37	
SMTP server43	
SNC audio upload tool68	
SNC video player70	
SNMP	
Software version	
software version	
special tags44	
subnet mask	
System	
system configuring31	
System log	
System log	
-	
Т	
TCP27	
-	
TCP27	
TCP	
TCP	
TCP 27 TCP/UDP 19, 27 time difference 32 Time zone 32 time zone 32	
TCP 27 TCP/UDP 19, 27 time difference 32 Time zone 32 time zone 32 title 43	
TCP 27 TCP/UDP 19, 27 time difference 32 Time zone 32 time zone 32	
TCP 27 TCP/UDP 19, 27 time difference 32 Time zone 32 title 43 title bar 31 Title bar name 31	
TCP 27 TCP/UDP 19, 27 time difference 32 Time zone 32 title 43 title bar 31 Title bar name 31 Trigger 19, 25, 30, 57	
TCP 27 TCP/UDP 19, 27 time difference 32 Time zone 32 title 43 title bar 31 Title bar name 31 Trigger 19, 25, 30, 57 trigger 19, 25, 30, 57	
TCP 27 TCP/UDP 19, 27 time difference 32 Time zone 32 title 43 title bar 31 Title bar name 31 Trigger 19, 25, 30, 57	
TCP 27 TCP/UDP 19, 27 time difference 32 Time zone 32 title 43 title bar 31 Title bar name 31 Trigger 19, 25, 30, 57 trigger 19, 25, 30, 57	
TCP 27 TCP/UDP 19, 27 time difference 32 Time zone 32 title 43 title bar 31 Title bar name 31 Trigger 19, 25, 30, 57 trigger setting Menu 57	
TCP	

V

View size	18, 20
view size	18, 20
viewer	16
Viewer mode	44
viewer mode	44
volume	19

W

welcome page.....11, 15, 31